# User's Guide: CSIM19 Simulation Engine (C Version)

Mesquite Software, Inc. PO Box 26306 Austin, TX 78755-0306 (512) 338-9153 Internet: info@mesquite.com

To navigate through this document, please use the list of bookmarks to the left.

A number of blank pages appear in this file. These pages have been included to preserve consistency with the page numbering in the printed version of this document.

# **Table of Contents**

1. Introduction	1
1.1 CSIM Objects	
1.2 Syntax Notes	
2. Simulation Time	5
2.1 Choosing a Time Unit	
2.2 Retrieving the Current Time	
2.3 Delaying for an Amount of Time	
2.4 Advancing Time	
2.5 Displaying the Time	
2.6 Integer-Valued Simulation Time	
3. Processes	11
3.1 Initiating a Process	
3.2 Executing the Process CREATE Statement	
3.3 Process Operation	
3.4 Terminating a Process	
3.5 Changing the Process Priority	
3.6 Inspector Functions	
3.7 Reporting Process Status	
4. Facilities	17
4.1 Declaring and Initializing a Facility	18
4.2 Using a Facility	
4.3 Reserving and Releasing a Facility	20
4.4 Producing Reports	
4.5 Resetting a Facility	21
4.6 Releasing a Specific Server at a Facility	23
4.7 Declaring and Initializing a Multiserver Facility	23
4.8 Facility Sets	
4.9 Reserving a Facility with a Time-out	25

	4.10 Renaming a Facility	25
	4.11 Changing the Service Discipline at a Facility	26
	4.12 Deleting a Facility or a Facility Set	29
	4.13 Collecting Class-Related Statistics	30
	4.14 Inspector Functions	
	4.15 Status Report	
5.	Storages	35
	5.1 Declaring and Initializing Storage	
	5.2 Allocating from a Storage	
	5.3 Deallocating from a Storage	
	5.4 Producing Reports	
	5.5 Resetting a Storage Unit	
	5.6 Storage Sets	
	5.7 Allocating Storage with a Time-out	
	5.8 Making a Storage Unit Clock Synchronous	
	5.9 Adding and Removing Storage Elements to a Storage Unit	
	5.10 Renaming a Storage Unit	
	5.11 Deleting Storage or a Storage Set	
	5.12 Inspector Functions	
	5.13 Reporting Storage Status	
6	Duffere	45
Ο.	. Buffers	
	6.1 Declaring and Initializing a Buffer	
	6.2 Putting Tokens into a Buffer	
	6.3 Getting Tokens from a Buffer	
	6.4 Producing Reports	
	6.5 Resetting a Buffer	
	6.6 Timed Operations for Buffers	
	6.7 Adding Capacity to a Buffer	
	6.8 Removing Capacity from a Buffer	
	6.9 Deleting a Buffer	
	6.10 Inspector Functions	
	6.11 Reporting Buffer Status	51
7.	. Events	
	7.1 Declaring and Initializing an Event	
	7.2 Waiting for an Event to Occur	54

7.3 Waiting with a Time-out	55
7.4 Queueing for an Event to Occur	55
7.5 Queueing with a Time-out	56
7.6 Setting an Event	56
7.7 Clearing an Event	57
7.8 Renaming an Event	57
7.9 Deleting an Event	58
7.10 Collecting and Reporting Statistics for Events	58
7.11 Resetting an Event	59
7.12 Event Sets	60
7.13 Inspector Functions	62
7.14 Status Report	63
7.15 Built-In Events	63
8. Mailboxes	6E
8.1 Declaring and Initializing a Mailbox8.2 Sending a Message	
8.3 Receiving a Message	
8.4 Receiving a Message with a Time-out	
8.5 Synchronous_send	
8.6 Synchronous_send with a Time-out	
8.7 Collecting and Reporting Statistics for Mailboxes	
8.8 Resetting a Mailbox	
8,9 Mailbox Sets	
8.10 Renaming a Mailbox	
8.11 Deleting a Mailbox	
8.12 Inspector Functions	
8.13 Status Report	
·	
9. Managing Queues	
9.1 Process Pointers and Process Structures	
9.2 Process Queues at Facilities	
9.3 Process Queues at Storages	
9.4 Process Queues at Buffers	
9.5 Process Queues at Events	
9.6 Process Queues and Message Lists at Mailboxes	82
10. Introduction to Statistics Gathering	85

11. Tables	87
11.1 Declaring and Initializing a Table	88
11.2 Tabulating Values	89
11.3 Producing Reports	
11.4 Histograms	
11.5 Confidence Interval	
11.6 Moving Windows	
11.7 Inspector Functions	
11.8 Renaming a Table	
11.9 Resetting a Table	
11.10 Deleting a Table	98
12. Qtables and Qtable_dbl's	99
12.1 Declaring and Initializing a Qtable	100
12.2 Noting a Change in Value	101
12.3 Producing Reports	102
12.4 Histograms	
12.5 Confidence Intervals	
12.6 Moving Windows	
12.7 Inspector Functions	
12.8 Renaming a Qtable	
12.9 Resetting a Qtable	
12.10 Deleting a Qtable	110
13. Meters	111
13.1 Declaring and Initializing a Meter	111
13.2 Instrumenting a Model	112
13.3 Producing Reports	113
13.4 Histograms	
13.5 Confidence Intervals	
13.6 Moving Windows	
13.7 Inspector Functions	
13.8 Renaming a Meter	
13.9 Resetting a Meter	
13.10 Deleting a Meter	118

14. Boxes	119
14.1 Declaring and Initializing a Box	119
14.2 Instrumenting a Model	
14.3 Producing Reports	121
14.4 Histograms	
14.5 Confidence Intervals	
14.6 Moving Windows	
14.7 Inspector Functions	
14.8 Renaming a Box	
14.9 Resetting a Box	
14.10 Deleting a Box	128
15. Advanced Statistics Gathering	129
15.1 Example: Instrumenting a Facility	
15.2 The Report Function	
15.3 Resetting Statistics	131
16. Confidence Intervals and Run Length Control	133
16.1 Confidence Intervals	
16.2 Inspector Functions	
16.2 Inspector Functions	136
·	136 138
16.3 Run Length Control	136 138 140
16.3 Run Length Control	136 138 140
16.3 Run Length Control	136 138 140 <b>141</b> 141
16.3 Run Length Control	136 140 141 141
16.3 Run Length Control	136 140 141 141 142
16.3 Run Length Control	136140141142143
16.3 Run Length Control	136140141142143143
16.3 Run Length Control	136140141142142143143
16.3 Run Length Control	136140141142143144144
16.3 Run Length Control	136141142143144144145
16.3 Run Length Control	136141142143144144145

18.3 Single Versus Multiple Streams	150
18.4 Managing Multiple Streams	150
18.5 Multiple Stream Random Number Generation	152
19. Output from CSIM	153
19.1 Generating Reports	154
19.1.1 Partial Reports	154
19.1.2 Complete Reports	155
19.1.3 To Change the Model Name	156
19.2 CSIM Report Output	157
19.2.1 Report_Hdr Output	158
19.2.2 Report_Facilities Output	159
19.2.3 Report_Storages Output	160
19.2.4 Report_Buffers Output	161
19.2.5 Report_Classes Output	162
19.2.6 Report_Events Output	163
19.2.7 Report_Mailboxes Output	164
19.2.8 Report_Tables Output	165
19.2.9 Report_Qtables Output	166
19.2.10 Report_Meters Output	168
19.2.11 Report_Boxes Output	168
19.3 Printing Model Statistics	169
19.3.1 To Generate a Report on the Model Statistics	169
19.3.2 Events processed	169
19.4 Generating Status Reports	170
19.4.1 Partial Reports	170
19.4.2 Complete Reports	171
20. Tracing Simulation Execution	173
20.1 Tracing all State Changes	
20.2 Tracing a Specific Process	
20.3 Tracing a Specific Object	
20.4 Format of Trace Messages	175

20.5 Program Generated Trace Messages	176
20.6 What Is and Is Not Traced	176
20.7 Redirecting Trace Output	177
21. Miscellaneous	179
21.1 Real Time	179
21.1.1 To retrieve the Current Real Time	180
21.1.2 To Retrieve the Amount of CPU Time Used by the  Model	100
21.2 Retrieving and Setting Limits	
21.2.1 To Retrieve or Change a CSIM Maximum	
21.3 Creating a CSIM Program	
21.3.1 To process CSIM input parameters from a user-	102
provided main() routine	182
21.3.2 To cause CSIM to perform its necessary cleanup	
when using a user-provided main() routine	183
21.4 Rerunning or Resetting a CSIM Model	
21.4.1 To Rerun a CSIM Model	183
21.4.2 To clear statistics without rerunning the model	184
21.4.3 Conclude_flag	185
21.5 Error Handling	185
21.5.1 To request that CSIM call a user-specific error handler	185
21.5.2 To request that CSIM revert to the default method	
of handling errors	186
21.5.3 To print the error message corresponding to the index	
passed to the error handler	
21.6 Output File Selection	
21.6.1 To change the file to which a given type of output is sent	
21.7 Compiling and Running CSIM Programs	
21.8 Reminders and Common Errors	
22. Error Messages	191
23. Acknowledgments	205
24. List of References	207

26. Statements, Reserved Words       215         26.1 Statements and Reserved Words       215         26.2 Data Structures       236         26.3 Constant Values       237         26.4 Special Structures       237         26.5 Legacy Functions       238	25. Sample Program	211
26.2 Data Structures       236         26.3 Constant Values       237         26.4 Special Structures       237	26. Statements, Reserved Words	215
26.3 Constant Values23726.4 Special Structures237	26.1 Statements and Reserved Words	215
26.4 Special Structures237	26.2 Data Structures	236
·	26.3 Constant Values	237
26.5 Legacy Functions238	26.4 Special Structures	237
	26.5 Legacy Functions	238

# 1. Introduction

CSIM+ is a process-oriented discrete-event simulation package for use with C programs. It is implemented as a library of routines which implement all of the necessary operations. The end result is a convenient tool which programmers can use to create simulation programs.

A CSIM program models a system as a collection of CSIM processes which interact with each other by using the CSIM structures. The purpose of modeling a system is to produce estimates of time and performance. The model maintains simulated time, so that the model can yield insight into the dynamic behavior of the modeled system.

This document provides a description of:

- CSIM structures (objects) and the statements that manipulate them
- Reports available from CSIM
- Information on compiling, executing and debugging CSIM programs.

1

<sup>+</sup> CSIM is copyrighted by Microelectronics and Computer Technology Corporation, 1987 - 1994

# 1.1. CSIM Objects

Every CSIM object is implemented in the same manner. For each CSIM structure, the program must have a declaration, which is a pointer to an object (an instance of the structure). Before an object can be used, it must be initialized by the constructor function for that kind of object. These serve the same functions as object declarations and constructors.

The structures provided in CSIM are as follows:

- Processes the active entities that request service at facilities, wait for events, etc. (i.e. processes deal with all of the other structures in this list)
- Facilities queues and servers reserved or used by processes
- Storage units resources which can be partially allocated to processes
- Buffers resources which can be partially allocated to processes; a buffer can be empty and/or partially full
- Events used to synchronize process activities
- Mailboxes used for inter-process communications
- Data collection structures used to collect data during the execution of a model
- Process classes used to segregate statistics for reporting purposes
- Streams streams of random numbers

It is the processes which mimic the behavior of active entities in the simulated system.

# 1.2. Syntax Notes

- All parameters are required.
- Whenever a parameter is included within double quotes (e.g. "name"), it can also be passed as a pointer to a character array which contains the string.

Constants, which are represented by names that are entirely in capital letters, are defined in the header file, "csim.h".

Time is an important concept in any performance model. CSIM maintains a simulation clock whose value is the current time in the model. This simulation time is distinctly different than the cpu time used in executing the model or the "real world" time of the person running the model. Simulation time starts at zero and then advances unevenly, jumping between times at which the state of the model changes. It is impossible to make time move backwards during a simulation run.

The simulation clock is implemented as a double precision floating point variable in CSIM. For most models there is no need to worry that the simulation clock will overflow or that round-off error will impact the accuracy of the clock.

The simulation clock is used extensively within CSIM to schedule events and to update performance statistics. CSIM processes may retrieve the current time for their own purposes and may indirectly cause time to advance by performing certain operations.

## 2.1. Choosing a Time Unit

The CSIM simulation clock has no predefined unit of time. It is the responsibility of the modeler to choose an appropriate time unit and to consistently specify all amounts of time in that unit. All performance statistics reported by CSIM should also be interpreted as being in that chosen time unit.

A good time unit might be close to the granularity of the smallest time periods in the model. For example, if the smallest time periods being modeled are on the order of tens of milliseconds, an appropriate time unit might be either milliseconds or seconds. Using microseconds or minutes as the time unit would produce performance statistics that are either very large or very small numbers.

Most numbers appearing in CSIM performance reports are printed with up to six digits to the left of the decimal point and six digits to the right of the decimal point. A time unit should be chosen to avoid numbers so large that they overflow their fields or so small that interesting digits are not visible.

# 2.2. Retrieving the Current Time

There are two equivalent ways to retrieve the current value of the simulation clock. One is to call the *simtime* function.

**Prototype:** double simtime(void)

**Example:** x = simtime();

The other is to reference the variable *clock*.

**Example:** x = clock; or

 $x = csim_clock;$ 

## 2.3. Delaying for an Amount of Time

A CSIM process can delay for a specified amount of simulation time by calling the *hold* function.

Prototype: void hold(double amount\_of\_time)

**Example:** hold(1.0);

If there are other processes waiting to run, the calling process will be suspended. Otherwise, time will immediately advance by the specified amount.

Caution: It is a common mistake to call hold with the wrong type of parameter, such as an integer value.

A process can delay until a specified point in simulated time by calling *hold* with a parameter value equal to the specified time minus the current time. To make a simulation begin with a clock value other than zero, simply call *hold* at the beginning of the *sim* function with an amount of time equal to the desired initial time.

Calling the *hold* function with a zero amount of time might at first seem to be meaningless. But, it causes the running process to relinquish control to any other process that is waiting to run at the same simulation time. This can be used to affect the order of execution of processes that have activities scheduled for the same simulation time.

# 2.4. Advancing Time

There is no way for a program to directly assign a value to the simulation clock. The simulation clock advances as a side effect of a process performing one of the following function calls.

hold	allocate	get
put	wait	queue
use	timed_allocate	timed_put
timed_get	wait_any	queue_any
reserve	receive	timed_wait
timed_queue	timed_reserve	timed_receive
synchronous_send	timed_synchron	ous_send

Calling one of these functions does not guarantee that time will advance. For example, calling the *allocate* function will cause time to pass only if the requested amount of storage is not available.

All CSIM function calls other than those in the above list, as well as all C language statements, occur instantaneously with respect to simulation time. A CSIM program can perform arbitrarily many activities in a single instant of simulation time.

A common programming error is to create a CSIM process that calls none of the functions in the above list. When this process receives control, it runs endlessly to the exclusion of all other CSIM processes.

# 2.5. Displaying the Time

There are several ways the simulation time can be automatically displayed while running a CSIM program. Every trace message contains the current simulation time. The variable *clock* and the function *simtime()* can be used to get the current simulated time. Also, when the *report* function is called to produce a report of all statistics, the report header contains the current simulation time.

# 2.6. Integer-Valued Simulation Time

In some simulation models, such as models of computer hardware, it is the case that time can only assume discrete integer values. Although CSIM maintains time as a floating point variable, some simple programming techniques can insure that the clock will always have an integer value. (Here, we are using the word "integer" in the mathematical sense.)

Amounts of time appear as input parameters in calls to the following functions: hold, use, timed\_reserve, timed\_allocate, timed\_put, timed\_get, timed\_receive, timed\_synchronous\_send, timed\_wait, timed\_queue, time\_wait\_any and timed\_queue\_any. To maintain an integer-valued clock, these parameters must have values that are integers (although of type double). This can be accomplished either by specifying a floating point numeric literal that has an integer value or by type casting an integer expression to type double.

```
Example: hold(10.0);
```

**Example:** use(bus, (double)uniform\_int(1,5));

**Example:** use(bus, (double)floor (exponential(1.0)));

The IEEE Floating Point Standard guarantees that addition and subtraction with integer valued operands will yield integer valued results. CSIM performs only addition on the simulation clock.

Processes represent the active entities in a CSIM model. For example, in a model of a bank, customers might be modeled as processes (and tellers as facilities). In CSIM, a process is a C procedure which executes a *create* statement. A CSIM process should not be confused with a UNIX process (which is an entirely different thing). The *create* statement is similar to a UNIX "fork" statement. A process can be invoked with input arguments, but it cannot return a value to the invoking process.

There can be several simultaneously "active" instances of the same process. Each of these instances appears to be executing in parallel (in simulated time) even though they are in fact executing sequentially on a single processor. The CSIM runtime package guarantees that each instance of every process has its own runtime environment. This environment includes local (automatic) variables and input arguments. All processes have access to the global variables of a program.

A CSIM process, just like a real process, can be in one of four states:

- Actively computing
- Ready to begin computing
- Holding (allowing simulated time to pass)
- Waiting for an event to happen (or a facility to become available, etc.)

When an instance of a process terminates, either explicitly or via a procedure exit, it is deleted from the CSIM system. Each process has a unique process id and each has a priority associated with it.

## 3.1. Initiating a Process

In CSIM, a process is a procedure which executes a *create* statement; a process is initiated (invoked, started, ...) by executing a standard procedure call:

```
Prototype: void proc(arg1, ..., argn);
```

**Example:** my\_proc(a, 64, "label");

In some cases, the process initiator requires the id of the initiated process. In these cases, the prototype and example appear as follows:

**Prototype:** long proc(arg1, . . ., argn);

**Example:** proc id = my proc(a, 32, "label");

*Caution*: It is bad practice to pass the address of a local variable to a CSIM process as an input argument.

Caution: A process cannot return a function value.

Caution: A create statement (see below) must appear in the initiated process.

# 3.2. Executing the Process CREATE Statement

As stated above, a CSIM process is a procedure which executes the *create* statement:

**Prototype:** void create(char\* name)

**Example:** create("customer");

The name of a process is just a character string which is used to identify the process in event traces and reports generated by CSIM. Typically, the *create* statement is executed at the beginning of a process. Each instance of a process is given a unique process id (process id's are not reused). Processes can invoke procedures and functions in any manner. Processes can also initiate other processes.

When a procedure executes its *create* statement, the following actions take place:

- The process executing the create statement (the called process) is established and is made "ready to execute" at the statement following the create statement, and
- The calling process continues its execution (i.e., it remains the
  actively computing process) at the statement after the
  procedure call to the called process.

The calling process continues as the active process until it suspends itself.

No simulated time passes during the execution of a *create* statement.

Note: process id's are 32 bit integers; if 2<sup>31</sup>-1 id's are used, the sequence of id's is reset to 2.

### 3.3. Process Operation

Processes appear to operate simultaneously with other active processes at the same points in simulated time. The CSIM process manager creates this illusion by starting and suspending processes as time advances and as events occur. Processes execute until they "suspend" themselves by doing one of the following actions:

• execute a hold statement (delay for a specified interval of time),

- execute a statement which causes the processes to be placed in a queue, or
- · csim terminate.

Processes are restarted when the time specified in a *hold* statement elapses or when a delay in a queue ends. It should be noted that simulated time passes only by the execution of *hold* statements. While a process is actively computing, no simulated time passes.

The process manager preserves the correct context for each instance of every process. In particular, separate versions of all local variables (variables resident in the runtime stack frame) and input arguments for a process are maintained. CSIM accomplishes this by saving and restoring process contexts (segments of the runtime stack) as processes suspend themselves and as processes are "resumed" (restored). A consequence of this kind of operation is that if one processes passes an address of a local variable to another process, it is likely that when this address is referenced, the reference will be invalid. The reason is that when a process is not actually computing (using the real CPU), its stack frame with the local variables will not be physically located in the correct place in memory. This is not a major obstacle to writing efficient and useful models; it is a detail which must be remembered as CSIM models are developed.

### 3.4. Terminating a Process

A process terminates when it either does a normal procedure exit or when it executes a *terminate* statement.

Prototype: void csim\_terminate(void)

**Example:** csim\_terminate();

The normal case is for a process to do a normal procedure exit or return. The *terminate* statement is provided when this normal case is not appropriate.

# 3.5. Changing the Process Priority

The initial priority of a process is inherited from the initiator of that process. For the sim (main) process, the default priority is 1 (low priority).

Prototype: void set\_priority(long new\_priority)

**Example:** set\_priority(5);

This statement must appear after the *create* statement in a process. Lower values represent lower priorities (*i.e.* priority 1 processes will run later than priority 2 processes when priority is a consideration in order of execution (see section 4.11, "Changing the Service Discipline at a Facility").

### 3.6. Inspector Functions

These functions each return some information to the process issuing the statement. The type of the returned value for each of these functions is as indicated.

Prototype: Functional Value:

char\* process\_name(void) retrieves pointer to name of

process

issuing inquiry

long identity(void) retrieves the identifier (process

number) of process issuing the

inquiry

long priority(void) retrieves the priority of process

issuing inquiry

# 3.7. Reporting Process Status

To print the status of each active process in a model:

**Prototype:** void status\_processes(void)

**Example:** status\_processes();

To print the status of processes with pending state changes (the "next event list"):

Prototype: void status\_next\_event\_list(void)

**Example:** status\_next\_event\_list();

These reports will be written to the default output location or to that specified by *set\_output\_file* (see section 19.7, "Output File Selection").

A facility is normally used to model a resource (something a process requests service from) in a simulated system. For example, in a model of a computer system, a CPU and a disk drive might both be modeled by CSIM facilities. A simple facility consists of a single server and a single queue (for processes waiting to gain access to the server). Only one process at a time can be using a server. A multiserver-server facility contains a single queue and multiple servers. All of the waiting processes are placed in the queue until one of the servers becomes available. A facility set is an array of simple facilities; in essence, a facility set consists of multiple single server facilities, each with its own queue.

Normally, processes are ordered in a facility queue by their priority (a higher priority process is ahead of a lower priority process). In cases of ties in priorities, the order is first-come, first-served (fcfs). An fcfs facility can be designated as a synchronous facility. Each synchronous facility has its own clock with a period and a phase and all *reserve* operations are delayed until the onset of the next clock cycle. Service disciplines other than priority order can be established for a server. These are described in section 4.11, "Changing the Service Discipline at a Facility".

A set of usage and queueing statistics is automatically maintained for each facility in a model. The statistics for all facilities which have been used are "printed" when either a *report* (see section 19.2, "CSIM Report Output") or a *report\_facilities* is executed (see section 4.4, "Producing Reports" for details about the reports that are generated). In addition, there is a set of inspector functions that can be used to extract individual statistics for each facility.

First time users of facilities should focus on the following four sections, which explain how to set up facilities, use (and reserve and release) facilities, and produce reports. Subsequent sections describe the more advanced features of facilities.

# 4.1. Declaring and Initializing a Facility

A facility is declared in a CSIM program using the built-in type FACILITY.

**Example:** FACILITY f;

Before a facility can be used, it must be initialized by calling the *facility* function.

**Prototype:** FACILITY facility(char\* name)

**Example:** f = facility("fac");

A newly created facility is created with a single server which is "free". The facility name is used only to identify the facility in output reports and trace messages.

Facilities should be declared with global variables and initialized in the first process (normally the process named *sim*) prior to the beginning of the simulation part of the model. Unless changed by a *set\_servicefunc* statement (see section 4.11, "Changing the Service Disciplines at a Facility"), the scheduling policy of the facility will be first-come, first-served (fcfs).

# 4.2. Using a Facility

A process typically uses a server for a specified interval of time.

**Prototype:** void use(FACILITY f, double service\_time)

**Example:** use(f, exponential(1.0));

If the server at this facility is free (not being used by another process), then the process gains exclusive use of the server and the usage interval starts immediately. At the end of the usage interval, the process gives up use of the server and departs this facility. Execution continues at the statement following the *use* statement.

If the server at this facility is busy (is being used by another process), then the newly arriving process is placed in a queue of waiting processes; this queue is ordered by process priority, with processes of equal priority being ordered by time of arrival. As each process completes its usage interval, the process at the head of the queue is assigned to the server and its usage interval starts at that time.

The service discipline at a facility specifies how processes are given access to the server. One of several different service disciplines can be specified for a facility. Also, another form of facility has multiple servers. In addition, it is possible to have an array of facilities (a facility set). The difference between a multiserver facility and a facility set is that a multiserver facility has one queue for all of the waiting processes, while a facility set has a separate queue for each facility in the set.

## 4.3. Reserving and Releasing a Facility

In some cases, a process will acquire a server, but will do something other than enter the usage interval when it gets the server. The statements for doing this are *reserve* (to gain exclusive use of a server) and *release* (to relinquish use of the server acquired in a previous *reserve* statement)

```
Prototypes: long reserve(FACILITY f) void release(FACILITY f)
```

**Examples:** reserve(f); release(f);

When a process executes a *reserve*, it either gets use of the server immediately (if the server is not busy) or it is suspended and placed in a queue of processes waiting to get use of the server. When it gains access to the server, it executes the statement following the *reserve* statement. The order of processes in the queue is by process priority, with processes of equal priority being ordered by time of arrival. This process priority service discipline is called fcfs in CSIM; it (along with *fcfs\_sy*, see below) is the only service discipline that can be specified for facilities where processes do this *reserve-release* style of access. If another service discipline is in force, then the processes must execute *use* statements instead of *reserve-release* pairs of statements.

The process releasing a server at a facility must be the same process as the one which reserved it. If this is not the case, then the *release\_server* statement (see below) must be used. When a process executes a *release*, it gives up use of the server; if there is at least one process waiting to start using the server (*i.e.*, there is at least one process in the queue at this facility), the process at the head of the queue is given access to the server and that process is then reactivated and will proceed by executing the statement following its reserve statement. No simulation time passes during execution of a release statement.

Note: Executing the sequence "reserve(f); hold(t); release(f);" is equivalent to executing the statement "use(f, t);". However, if the usage interval is specified by a random number function, then there is a subtle difference between these, as follows: the randomly derived interval is determined *after* gaining access to the server in the first sequence and *before* gaining access to the server with the *use* form; thus it is likely that the intervals in these two examples will be different. In other words, the sequence "reserve(f); hold (exponential (t)); release(f);" will not necessarily display exactly the same behavior as executing the statement "use(f, exponential (t));".

## 4.4. Producing Reports

Reports for facilities are most often produced by calling the *report* function which prints reports of all the CSIM objects. Reports can be produced for all existing facilities by calling the *report\_facilities* function.

Prototype: void report\_facilities(void)

Example: report\_facilities();

The report for a facility, as illustrated below, includes, for each facility, the name of the facility, the service discipline, the average service time, the utilization, the throughput rate, the average queue length, the average response time and the number of completed service requests.

FACILITY SUMMARY							
facility name	service disc	service time	util.	through put	queue length	response time	compl count
f	fcfs	0.40907	0.208	0.50900	0.27059	0.53162	509
ms fac	fcfs	1.50020	0.764	0.50900	0.83821	1.64678	509
> server	0	1.55358	0.494	0.31800			318
> server	1	1.41133	0.270	0.19100			191
q	rnd_rob	0.73437	0.507	0.69000	0.95522	1.38438	690

# 4.5. Resetting a Facility

In some cases, it is necessary to reset the statistics counters for a specific facility.

Prototype: void reset\_facility(FACILITY f)

**Example:** reset\_facility(f);

Executing this statement does not affect the state of the facility or its servers. The "reset" and the reset\_facilities statements each call reset\_facility() for all facilities in the model.

### 4.6. Releasing a Specific Server at a Facility

Sometimes, it is necessary for one process to reserve a facility and then for another process to release the server obtained by the first process. In this case, the first process has to save the index of the server it obtained, and then give this server index to the second process, so that it can specify that index in the *release\_server* statement, as follows:

**Example:** server\_index = reserve(f);

**Prototype:** void release\_server(FACILITY f, long

server\_index)

**Example:** release\_server(f, server\_index);

This operates in the same way as the *release* statement except that the ownership of the server is not checked; thus, a process which did not reserve the facility may release it by executing the *release server* statement with a server index.

## 4.7. Declaring and Initializing a Multiserver Facility

In some cases, a facility has multiple servers, and each of these servers is indistinguishable from the other servers. A multiserver facility is declared as a normal (single server) facility.

**Example:** FACILITY cpu;

However, a multiserver facility is initialized in a different manner.

**Prototype:** FACILITY facility\_ms(char \*name, long

number\_of\_servers)

```
Example:
             cpu = facility_ms("dual cpu", 2);
```

A process can either execute a use statement or the reserverelease pair of statements at a multiserver facility. In either case, the process gains access to any server that is free; a process is suspended and put in the single queue at the facility only when all of the servers are busy.

## 4.8. Facility Sets

A facility set is an array of facilities.

Example: FACILITY disk[10] A facility set is initialized as follows:

Prototype: void facility set(FACILITY f[], char \*name, long num\_facilities) ;

Example: facility\_set(disk, "disk", 10);

reserve(disk[0]);

In a facility set, each element of the set is an independent, single server facility, with its own queue. Each of these facilities is given a constructed name which shows its position in the set. In the above example, the name for the first element of the set is "disk[0]". Facility sets are used to model cases where each server has its own queue of waiting processes.

# 4.9. Reserving a Facility with a Time-Out

Sometimes a process must not wait indefinitely to gain access to a server. If a process executes the *timed\_reserve* function, it will be suspended until either it gains use of a server or the specified time-out interval expires.

```
Prototype: long timed_reserve(FACILITY f, double
timeout)
```

Example: result = timed\_reserve(f, 100.0);
 if (result ! = TIMED OUT) . . .

The process must check the functional value, to determine whether or not it obtained a server. If the value TIMED\_OUT is returned, the process did not obtain a server. If this is not returned (EVENT\_OCCURRED will in fact be returned), then the process did obtain a server and should eventually release the server.

# 4.10. Renaming a Facility

The name of a facility can be changed at any time, as follows:

**Example:** set\_name\_facility(f, "cpus");

Only the first ten characters of the facility's name are stored.

## 4.11. Changing the Service Discipline at a Facility

The service discipline for a facility determines the order in which processes at the facility are given access to that facility. If not otherwise specified, the service discipline for a facility is fcfs. When the priorities differ, processes gain access to the server in priority order (higher priority processes before lower priority processes). When processes have the same priority, the processes gain access in the order of their arrival at the facility (first come, first served). This default service discipline can be changed.

**Example:** set servicefunc(f, pre res);

Set\_servicefunc() refers to a service function which is invoked when the *use* statement (described above) references this facility. This service function can be any of the following pre-defined service discipline functions:

fcfs - first come, first served

This is the default service discipline and is described in the introduction to this section. If the *synchronous\_facility* statement (see below) is used for this facility, this will behave like a *fcfs\_sy* (clock synchronized fcfs) facility. In other words, there are two ways for a facility to become synchronized: specifying the service discipline of *fcfs\_sy* or specifying (or defaulting) fcfs for the service discipline and using the *synchronous\_facility* statement.

fcfs\_sy - first come, first served, clock synchronized

This is the same as fcfs except that requests can be satisfied only at the beginning of a clock cycle. If not otherwise specified (via *synchronous\_facility* below), the clock phase (time to onset of first clock cycle) will be 0.0, and the period (length of a clock cycle) will be 1.0.

inf srv - infinite servers

There is no queueing delay at all since there is always a server available at the facility.

lcfs\_pr - last come, first served, preempt

Arriving processes are always serviced immediately, preempting a process that is currently being served if necessary. Priority is not a consideration with this service discipline.

prc\_shr - processor sharing

This is load-dependent processor sharing. Service times for each process are determined based on the number of processes at the facility. If not otherwise specified (see  $set\_loaddep$  below), it will be assumed that the rate that applies when there are n processes at the facility is n (in other words, if there are n processes at the facility, the service time will be multiplied by n). The altered service times are recomputed as tasks that arrive at and leave the facility. There is no queueing delay with processor sharing since the assumption is that the server works faster and faster as necessary to service all processes that request it.

There can be a maximum of 100 processes sharing a *prc\_shr* facility.

#### pre\_res - preempt resume

Higher priority processes will preempt lower priority processes, so that the highest priority process at the facility will always finish using it first. Where the priorities are the same, processes will be served on a first come, first served basis. Preempted processes will eventually resume and complete their service time intervals.

#### pre\_rst - preempt-restart

Higher priority processes will preempt lower priority processes, so that the highest priority process at the facility will always finish using it first. Where the priorities are the same, processes will be served on a first come, first served basis. Preempted processes will eventually resume and will restart their respective service time intervals each time they resume.

#### rnd\_pri - round robin with priority

Higher priority processes will be served first. When there are multiple processes with the same priority, they will be serviced on a round robin basis, with each getting the amount of time specified in *set\_timeslice* (see below) before being preempted by the next process of the same priority.

#### rnd\_rob - round robin

Processes will be serviced on a round robin basis, with each getting the amount of time specified in *set\_timeslice* (see below) before being preempted by the next process requiring service. Process priority is not a consideration with this service discipline.

Caution: The use statement (as opposed to the reserve) statement must be used for most of these service disciplines to be effective. Only fcfs and fcfs\_sy will operate properly with reserve.

To set the clock information for the fcfs sy service discipline:

**Prototype:** void synchronous\_facility(FACILITY f, double

phase, double period)

**Example:** synchronous\_facility(f, 0.0, 1.0);

To set the load dependent service rate for the *prc\_shr* (see above) service discipline:

**Example:** set\_loaddep(f, rate, 10);

The "rate" array is an array of length n, where each element specifies the service rate for the corresponding number of processes using the server. Rate[i] is the amount by which the service time is multiplied when there are i processes at the facility. If n is less than the 100 (the maximum number of processes allowed to share use of a  $prc\_shr$  facility), then the value of the last specified rate is replicated until 100 values are available. Also, if n is greater than 99, only 100 values will be used. It should be remembered that the altered service times are recomputed as tasks arrive at and leave the facility.

To set the time slice for the round robin service disciplines, *rnd\_pri* and *rnd\_rob* (see above):

**Prototype:** void set\_timeslice(FACILITY f, double

slice\_length)

**Example:** set\_timeslice(f, 0.01);

### 4.12. Deleting a Facility or a Facility Set

To delete a facility:

Prototype: void delete\_facility(FACILITY f)

**Example:** delete\_facility(f);

To delete a facility set:

Prototype: void delete\_facility\_set(FACILITY if\_set[])

**Example:** delete\_facility\_set(f\_set);

Caution: Deleting a facility or facility set is an extreme action and should be done only when necessary.

# 4.13. Collecting Class-Related Statistics

Information about usage of a facility by processes belonging to different process classes can be collected for all facilities or for a specific facility. To collect class-based usage information for a specific facility:

Prototype: void collect\_class\_facility(FACILITY f)

**Example:** collect\_class\_facility(f);

Usage of this facility by all process classes (see section 17, "Process Classes") will be reported in the facilities report. Also, it is an error to change the maximum number of classes allowed after this statement has been executed.

To collect usage information for all facilities:

Prototype: void collect\_class\_facility\_all(void)

**Example:** collect\_class\_facility\_all();

This applies to all of the facilities in existence when this statement is executed Usage of the facilities by all process classes (see section 17, "Process Classes") will be reported in the facilities report. It is an error to change the maximum number of classes allowed after this statement has been executed.

#### 4.14. Inspector Functions

All statistics and information maintained by a facility can be retrieved during execution of a model or upon its completion.

Prototype:	Functional Value:
char* facility_name(FACILITY f)	pointer to name of facility
long num_servers(FACILITY f)	number of servers at facility
char* service_disp(FACILITY f)	pointer to name of service discipline at facility
double timeslice(FACILITY f) facility	time in each time-slice for
·	(which has a round robin service discipline)
long num_busy(FACILITY f)	number of servers currently busy at facility
long qlength(FACILITY f)	number of processes currently waiting at facility

long status(FACILITY f)	current status of facility Busy if all servers are in use FREE if at least one server is not in use
long completions(FACILITY f)	number of completions at facility
long preempts(FACILITY f)	number of preempted requests at facility
double qlen(FACILITY f)	mean queue length at facility
double resp(FACILITY f)	mean response time at facility
double serv(FACILITY f)	mean service time at facility
double tput(FACILITY f)	mean throughput rate at facility
double util(FACILITY f)	utilization (% of time busy) at facility

Additional data on servers and classes can be obtained as follows:

long server\_completions(FACILITY f, long sn) number of completions for server sn at facility

double server\_tput(FACILITY f, long sn)

mean throughput rate for server sn at facility

double server\_util(FACILITY f, long sn)

utilization for server sn at facility

long class\_qlength(FACILITY f, CLASS c)
number of processes from class at facility

 $\label{long_class_completions} $$ \c CIASS c)$ number of completions for class at facility$ 

 $\begin{array}{c} \text{double class\_qlen(FACILITY f, CLASS c)} \\ \text{mean queue length for class at facility} \end{array}$ 

## 4.15. Status Report

To obtain a report on the status of all of the facilities in a model:

Prototype: void status\_facilities (void)

Example: status\_facilities ();

This report lists each facility along with the number of servers, the number of servers which are busy, the number of processes waiting. the name and id of each process at a server, and the name and id of each process in the queue.

A CSIM storage is a resource which can be partially allocated to a requesting process. A storage consists of a counter (to indicate the amount of available storage) and a queue for processes waiting to receive their requested allocation. A storage set is an array of these basic storages.

A storage can be designated to be synchronous. In a synchronous storage, each allocate is delayed until the onset of the next clock cycle.

Usage and queueing statistics are automatically maintained for each storage unit. These are "printed" whenever a *report* or a *report\_storages* statement is executed (see section 19.2, "CSIM Report Output" for details about the reports that are generated).

### 5.1. Declaring and Initializing Storage

A storage is declared in a CSIM program using the built-in type STORE.

**Example:** STORE s;

Before a storage can be used, it must be initialized by calling the *storage* function.

Prototype: STORE storage(char\* name, long size)

**Example:** s = storage("memory", 1000);

A newly created storage is created with all of the "storage" available. Storages should be declared with global variables in the sim (main) process, prior to the beginning of the simulation part of the model. A storage must be initialized via the *storage* statement before it can be used in any other statement.

## 5.2. Allocating from a Storage

The elements of a storage can be allocated to a requesting process.

**Prototype:** void alloc(STORE s, long amount)

**Example:** alloc(s, 10);

The amount of storage requested is compared with the amount of storage available at s. If the amount of available storage is sufficient, the amount available is decreased by the requested amount and the requesting process continues. If the amount of available storage is not sufficient, the requesting process is suspended. When some of the storage elements are deallocated by some other process, the highest priority waiting processes are automatically allocated their requested storage amounts (as they can be accommodated), and they are allowed to continue. The list of waiting processes is searched in priority order until a request cannot be satisfied. In order to preserve priority order, a new request which would fit but which would get in front of higher priority waiting requests will be queued.

Earlier versions of CSIM used an alternative statement to accomplish this function:

Prototype: void allocate(long amount, STORE s)

**Example**: allocate(10, s);

Caution: The order of the arguments for the allocate statement (and the deallocate statement too) can be confusing. Think of "allocating n elements of storage from storage s". The alternative form is included to accommodate legacy models.

## 5.3. Deallocating from a Storage Unit

To return storage elements to a storage, the deallocate procedure is used.

**Prototype:** void dealloc(STORE s, long amount)

**Example:** dealloc(s, 10);

If there are processes waiting, the highest priority processes that are waiting are examined. Those that will now fit have their requests satisfied and are allowed to continue. Executing a deallocate statement causes no simulated time to pass.

Caution: There is no check to insure that a process returns only the amount of storage that it had been previously allocated.

An alternative form of the dealloc statement is provided:

**Prototype:** void deallocate(long amount, STORE s)

**Example:** deallocate(s, 10);

The alternative form is included to accommodate legacy models.

### 5.4. Producing Reports

Reports for storages are most often produced by calling the *report* function, which reports for all CSIM objects. Reports can be produced for all existing storages by calling the *report\_storages* function. The report for a storage, as illustrated below, summarizes usage of and queueing for the storage units.

STORAGE SUMMARY								
storage name	size	alloc amount	alloc count	dealloc amount	dealloc count	util	in-que length	in-queue time
store	120	33.6	100335	30.0	100333	0.751	7.94470	7.91818

### 5.5. Resetting a Storage Unit

In some cases, it is necessary to reset the statistics counters for a specific storage unit.

Prototype: void reset\_storage(STORE s)

**Example:** reset\_storage(s);

Executing this statement does not affect the state of the storage. The "reset" and the reset\_storages statements each call reset\_storage() for all storage units in the model.

#### 5.6. Storage Sets

A storage set is an array of storages. Each element of the array is an individual storage.

**Example:** STORE \*s\_set; char \*name[5];

A storage set must be initialized before the elements of the set can be used.

**Prototype:** void storage\_set( STORE\* s\_set. char

\*name, long amount, long number\_in\_set);

**Example:** storage\_set(s\_set, "set", 100, 5);

The example initializes a set of five storages, each with 100 elements of storage available at the onset of operation. The name is the name of the set. Each individual unit of storage is given a unique (indexed) name. In the example, the first storage in the set is named "set[0]", the second is named "set[1]", and so on. The last storage is named "set[99]". Similarly, the individual units of storage are accessed as elements of an array. All of the operations which apply to a storage also apply to the individual units of a storage set.

### 5.7. Allocating Storage with a Time-Out

Sometimes, processes cannot wait indefinitely to allocate the needed amount of storage. If such a process executes the *timed\_allocate* function, then, if the requested amount of storage is not available, the process will be suspended until either the requested amount of storage becomes available or the time-out interval expires.

```
Example: result = timed_alloc(s, 10, 100.0);
    if (result ! = TIMED OUT) . . .
```

The process must check the function value (result) to determine whether or not the requested storage was obtained. If the value TIME\_OUT is returned, the process did not obtain any of the requested storage. If this value is not returned (EVENT\_OCCURRED will in fact be returned), then the process did obtain the requested storage.

An alternative form of the timed\_alloc statement is provided:

Prototype: void timed\_allocatelong amount, STORE s,

double timeout)

**Example:** result = timed allocate(s, 10, 100.0);

The alternative form is included to accommodate legacy models.

## 5.8. Making a Storage Unit Clock Synchronous

A storage unit can be designated to be a synchronous storage unit.

**Prototype:** void synchronous\_storage(STORE s,

double.phase,double period)

**Example:** synchronous\_storage(s, 0.0, 1.0);

A synchronous storage unit is similar to a normal storage unit except that allocation requests are always delayed until the beginning of the next clock cycle. The clock phase specifies the interval before the onset of the first clock cycle, and the period specifies the interval between successive clock cycles.

# 5.9. Adding and Removing Storage Elements to a Storage

To increase the amount of storage (the number of storage elements) in a storage unit,

Prototype: void add\_more\_store(STORE s, long amt)

**Example:** add\_more\_store(s, 100);

Earlier versions of CSIM used an alternative statement to add more storage to a storage unit; the alternative form is included to accommodate legacy models.:

Prototype: void add\_store(long amount, STORE s)

**Example:** add\_store(100, s);

To decrease the amount of storage (the number of storage elements):

Prototype: void remove\_store(STORE s, long amt)

**Example:** remove\_store(s, 100);

# 5.10. Renaming a Storage Unit

The name of a storage can be changed at any time, as follows:

Prototype: void set\_name\_storage(STORE s, char

\*new\_name)

**Example:** set\_name\_storage(s, "cache");

Only the first ten characters of the storage's name are stored.

# 5.11. Deleting Storage or a Storage Set

To delete a storage:

Prototype: void delete\_storage(STORE s)

**Example:** delete\_storage s);

To delete a storage set:

Prototype: void delete\_storage\_set(STORE s\_set[])

**Example:** delete\_storage(s\_set);

Deleting a storage or storage set is an extreme action and should be done only when necessary.

#### 5.12. Inspector Functions

These functions each return a statistic which describes some aspect of the usage of the specified storage.

Prototype: Functional Value:

 $\hbox{char* storage\_name}(\hbox{\tt SIORE s}) \hspace{1cm} \hbox{pointer to name of store}$ 

 $\hbox{long storage\_capacity}(\hbox{\tt STORE s}) \qquad \quad \hbox{number of storages defined for}$ 

store

number of storages currently long avail (STORE s) available at store number of processes currently long storage glength(STORE s) waiting at store sum of requested amounts from double storage\_request\_amt(STORE s) store time-weighted sum of long storage number amt(STORE s) requesters for store double storage busy amt(STORE s) busy time-weighted sum of amounts for store double storage\_waiting\_amt(STORE s) waiting time weighted sum of amounts for store total number of requests for long storage\_request\_cnt(STORE s) store total number of completed long storage release cnt(STORE s) requests for store number of queued requests at long storage\_queue\_cnt(STORE s) store double storage time(STORE s) time at store that is spanned by report

## 5.13. Reporting Storage Status

Prototype: void status\_storages (void)

**Example:** status\_storages ();

.

A CSIM buffer is a resource which can store (hold) a number of tokens. The primary operations for a buffer are *put*, which places a number of tokens into the buffer, and *put*, which removes a number of tokens from the buffer. A buffer has a maximum capacity for holding tokens. A *get* operation stalls if there are too few tokens in the buffer, and a *put* operation stalls if there is not enough space (unused capacity) in the buffer.

A buffer consists of a counter (indicating the number of tokens in the buffer), and two queues: a put-queue, for processes waiting to complete a put operation and a get-queue, for processes waiting to complete a get operation.

Usage and queueing statistics are automatically maintained for each buffer. These are "printed" whenever a *report* or *report\_buffers* statement is executed (see section 19.2 "CSIM Report Output" for details about the reports that are generated).

# 6.1. Declaring and Initializing a Buffer

A buffer is declared in a CSIM program using the built-in type BUFFER.

**Example:** BUFFER b;

Before a buffer can be used, it must be initialized by calling the buffer function. Prototype:

BUFFER buffer(char \*name, long size);

**Example:** b = buffer("b", 10);

A newly created buffer is empty. Buffers should be declared with global variables in the sim (main) process, prior to beginning the simulation part of the model. A buffer must be initialized via the buffer statement before it can be used in any other statement.

### 6.2. Putting Tokens into a Buffer

Tokens can be added to a buffer using the *put* operation.

Prototype: void buffer\_put(BUFFER b, long amt);

**Example:** buffer\_put(b, 5);

The number of tokens being put (the amount) is compared with the space remaining in the buffer (the maximum size minus the current amount). If the available space is less than or equal to space

remaining, the amount of the put is added to the current amount and the process doing the buffer\_put continues. If the amount of the put exceeds the space remaining, the process is placed in the put-queue and is then suspended. When some other process (or processes) removes (gets) tokens, the highest priority process in the put-queue is checked; if its put request can be accommodated, the buffer\_put is done and the process resumes at the statement following the buffer\_put statement. If other processes in the put-queue can be accommodated, they too are processed and allowed to proceed.

## 6.3. Getting Tokens from a Buffer

Tokens can be removed a buffer using the buffer-get statement.

Prototype: void buffer\_get(BUFFER b, long amt);

**Example:** buffer\_get(b, 4);

The number of tokens being requested in a get (the amount) is compared to the number in the buffer. If the amount is less than or equal to the number in the buffer, the amount is subtracted and the process doing the buffer\_get proceeds. If not, the process doing the buffer\_get is placed in the get-queue and then suspended. When another process (or processes) puts (adds) tokens to the buffer, the highest priority process in the get-queue is checked; if its get request can be satisfied, the buffer\_get is done, and the process resumes at the statement following the buffer\_get. If other processes in the get-queue can be accommodated, they too are processed and allowed to proceed.

### 6.4. Producing Reports

Reports for buffers are most often produced by calling the *report* function which reports for all CSIM objects. Reports can be produced for all existing buffers by calling *report\_buffers* function. The report for a buffer gives the name of the buffer,

#### **BUFFER SUMMARY**

buffer		get	get	get	get	put	put	put	put
name	size	amt	qlen	resp	count	amt	qlen	resp	count
buff	20	2.4	0.00000	0.00000	32	3.5	1.54545	0.60714	28

# 6.5. Resetting a Buffer

In some cases, it is necessary to reset the statistics counters for a specificbuffer.

**Prototype:** void reset\_buffer(BUFFER b)

**Example:** reset\_buffer(b);

Executing this statement does not affect the state of the buffer or its servers. The "reset" and the reset\_buffers" statements each call reset buffer() for all buffers in the model.

### 6.6. Timed Operations for Buffers

Sometimes, processes cannot wait indefinitely to either get tokens form or putting tokens into a buffer.

**Example:** result = buffer\_timed\_get(b, 5, 100.0);

if(result != TIMED\_OUT) . . .

and

Prototype: long buffer\_timed\_put(BUFFER b, long amt,

double timeout);

**Example:** result = buffer\_timed\_put(b, 5, 100.0);

if(result != TIMED OUT) . . .

The process must check the function value (result) to determine whether or not the operation completed or timed-out. If the value TIME\_OUT is returned, the process did not obtain any of the requested storage. If this value is not returned (EVENT\_OCCURRED will in fact be returned), then the process did obtain the requested storage.

# 6.7. Adding Capacity to a Buffer

To increase the space (capacity) for a buffer,

Prototype: void buffer\_add\_space(BUFFER b, long amt);

**Example:** buffer\_add\_space(b, 25);

## 6.8. Removing Capacity from a Buffer

To remove space (capacity) from a buffer,

**Prototype:** void buffer\_remove\_space(BUFFER b, long

amt);

**Example:** buffer\_remove\_space(b, 2);

## 6.9. Deleting a Buffer

To delete a buffer:

Prototype: void delete\_buffer(BUFFER b);

**Example:** delete buffer(b);

Deleting a buffer is an extreme action and should be done only when

necessary.

# 6.10. Inspector Functions

These functions each return a statistic or counter value which describes some aspect of the operation of a buffer:

Prototype: Function Value:

```
long buffer current(BUFFER b)
                                 current number of tokens
long buffer size(BUFFER b)
                                capacity of buffer
long buffer get total (BUFFER b) total amount retrieved
long buffer put total (BUFFER b) total amount put
long buffer_get_count(BUFFER b) number of get's
long buffer put count(BUFFER b) number of put's
double buffer get timeQueue(BUFFER b) sum of get-
                                   queue lengths
double buffer put timeQueue(BUFFER b) sum of get-
                                    queue lengths
char* buffer_name(BUFFER b) name of buffer
long buffer get current count (BUFFER b) current get-
                                   queue length
long buffer put current count (BUFFER b) current put-
                                   queue length
```

# 6.11. Reporting Buffer Status

**Prototype:** void status buffers(BUFFER b);

**Example:** status buffers(b);

The report will be written to the default output location or to that specified by  $set\_output\_file$  (see section xx.x, "Output File Selection").

Events are used to synchronize the operations of CSIM processes. An event exists in one of two states: *occurred or not occurred*. A process can change the state of an event, or it can suspend its execution until an event has occurred. When a process is suspended it can join a set of processes, all of which will be resumed when the event occurs. Or, it can join an ordered queue from which only one process is resumed for each occurrence of the event. An event is automatically reset to the *not occurred* state when all of the suspended processes that can proceed have done so.

Advanced features of events include the ability to create sets of events for which processes can wait and the ability for a process to bound its waiting time by specifying a time-out. Events can also be used to construct other synchronization mechanisms such as semaphores.

## 7.1. Declaring and Initializing an Event

An event is declared in a CSIM program using the built-in type EVENT.

**Example:** EVENT e;

Before an event can be used, it must be initialized by calling the *event* function.

**Prototype:** EVENT event(char\* name)

**Example:** e = event("done");

An event is initialized in the *not occurred* state. The event name is used only to identify the event in output reports and trace messages.

An event that is initialized in the first CSIM process (sim) exists during the entire simulation run and is called a global event. An event initialized in any other process is called a local event. A local event is deleted when the process in which it was initialized terminates. To make such an event exist for the entire run, it must be initialized by calling the <code>global\_event</code> function.

**Prototype:** EVENT global\_event(char\* name)

**Example:** e = global\_event("done");

#### 7.2. Waiting for an Event to Occur

A process waits for an event to occur by calling the *wait* function.

Prototype: void wait(EVENT e)

Example: wait(e);

If the event is in the *occurred* state, control returns from the *wait* function immediately and the event is changed to the *not occurred* state. If the event is in the *not occurred* state, the calling process is suspended from further execution and control will not return from the *wait* function until some other process sets this event. When the event is set, all waiting processes will be resumed and the event will be placed in the *not occurred* state.

### 7.3. Waiting with a Time-Out

Sometimes a process must not be suspended indefinitely waiting for an event to occur. If a process calls the *timed\_wait* function, it will be suspended until either the event is set or the specified amount of time has passed.

Prototype: long timed\_wait(EVENT e, double timeout)

Example: result = timed\_wait(e, 100.0);
 if (result ! = TIMED OUT)

The calling process should check the functional value to determine the circumstances under which it was resumed. If the value EVENT\_OCCURRED is returned, the process was activated because the event has occurred; if the value TIMED\_OUT is returned, the specified amount of time passed without the event being set.

### 7.4. Queueing for an Event to Occur

A process joins the ordered queue for an event by calling the *queue* function.

**Prototype:** void queue(EVENT e)

**Example:** queue(e);

This function behaves similarly to the *wait* function, except that each time the event is set only one queued process is resumed. The queue is maintained in order of process priority, with processes having the same priority being ordered by time of insertion into the queue.

### 7.5. Queueing with a Time-Out

If a process calls the *timed\_queue* function, it will be suspended until either the event is set a sufficient number of times for the process to be activated or the specified amount of time has passed.

**Prototype:** long timed\_queue(EVENT e, double timeout)

Example: result = timed\_queue(e, 100.0);
 if (result ! = TIMED OUT) ...

The calling process should check the functional value to determine the circumstances under which it was resumed. If the value EVENT\_OCCURRED is returned, the process was activated because the event occurred; if the value TIMED\_OUT is returned, the specified amount of time passed without the process being activated by the event being set.

#### 7.6. Setting an Event

A process can put an event into the *occurred* state by calling the *set* function.

**Prototype:** void set(EVENT e)

**Example:** set(e);

Calling this function causes all waiting processes and one queued process to be resumed. If there are no waiting or queued processes, the event will be in the *occurred* state upon return from the *set* function. If there are waiting or queued processes, the event will be in the *not occurred* state upon return. No simulation time passes

during these activities. Setting an event that is already in the occurred state has no effect.

## 7.7. Clearing an Event

A process can put an event into the *not occurred* state by calling the *clear* function.

**Prototype:** void clear(EVENT e)

**Example:** clear(e);

Clearing an event happens in zero simulation time and no processes are in any way affected. Clearing an event that is already in the *not occurred* state has no effect.

### 7.8. Renaming an Event

The name of an event can be changed at any time using the set\_name\_event function.

Prototype: void set\_name\_event(EVENT e, char \*new\_name)

**Example:** set\_name\_event(e, "finished");

Only the first ten characters of the event's name are stored.

### 7.9. Deleting an Event

When an event is no longer needed, its storage can be reclaimed using the *delete\_event* function.

Prototype: void delete\_event(EVENT e)

**Example:** delete\_event(e);

If an event is local, only the process that created the event can delete it. Once an event has been deleted, it must not be further referenced. It is an error to attempt to delete an event on which processes are waiting or queued.

#### 7.10. Collecting and Reporting Statistics for Events

A set of statistics on the usage can be collected for specified events. Statistics collection for an event is initiated by executing the event\_monitor statement.

Prototype: void event\_monitor(EVENT e)

**Example:** event\_monitor(e);

The standard report function automatically proceeds to "print" a report for each monitored event. This report is as follows:

**EVENT SUMMARY** 

event name	number of queue vst	0 1	0	number of wait vsts	0	J	
ev	10	0.99010	1.00000	50	4.95050	1.00000	10

A report for all of the monitored events can be generated as follows:

Prototype: void report\_events()

**Example:** report\_events();

All of the events in an event\_set (see below) can be monitored as well.

Prototype: void event\_set\_monitor(EVENT es[])

**Example:** event\_set\_monitor(es);

# 7.11. Resetting an Event

In some cases, it is necessary to reset the statistics counters for a specific event.

Prototype: void reset\_event(EVENT e)

**Example:** reset\_event(e);

Executing this statement does not affect the state of the event. The "reset" and the reset\_events statements each call reset\_event() for all events in the model.

#### 7.12. Event Sets

An event set is an array of related events for which some special operations are provided. An event set is declared using the C array construct.

```
Example: EVENT e_set[10];
```

All events in an event set are initialized with a single call to the event\_set function.

```
Example: event_set(e_set, "events", 10);
```

As with any C array, the events in an event set are indexed from *0* to *num\_events - 1*. Individual events in the event set can be manipulated using any of normal event functions (*e.g.*, set, clear, wait, queue).

```
Example: set(e_set[3]);
```

A process can wait for the occurrence of any event in an event set by calling the *wait\_any* function.

```
Prototype: long wait_any(EVENT e_set[])
Example: event_index = wait_any(e_set);
```

This function returns the index of the event that caused the calling process to proceed. If multiple events in the set are in the *occurred* state, the lowest numbered event is the one recognized by the calling process. All processes that have called *wait\_any* are activated by the next event that occurs, and these processes all receive the same index value.

A process can join an ordered queue for an event set by calling the *queue any* function.

```
Prototype: long queue_any(EVENT e_set[])
```

```
Example: event_index = queue_any(e_set);
```

Each time any event in the event set occurs, one process in the queue is activated. The functional value is the same as that of the *wait\_any* function. It is not currently possible to specify a time-out for the *wait\_any* or *queue\_any* functions.

An entire event set is deleted by calling the *delete\_event\_set* function.

```
Prototype: void delete_event_set(EVENT e_set[])
```

```
Example: delete_event_set(e_set);
```

The *delete\_event* function must not be called on individual members of an event set.

A process can also do a timed\_wait\_any() operation at an event set.

```
Prototype: long timed_wait_any(EVENT e_set[], double
to)
```

. .

```
Example: result = time_wait_any(e_set, 1.0);
    if(result != TIMED OUT) . . .
```

If the result is not equal to TIMED\_OUT, then it is the index of the event which caused the process to continue.

A process can also do a timed\_queue\_any() operation at an event\_set.

```
Prototype: long timed_queue_any(EVENT e_set[], double
to)
```

```
Example: result = time_queue_any(e_set, 1.0); if(result != TIMED_OUT) . . .
```

If the result is not equal to TIMED\_OUT, then it is the index of the event which caused the process to continue.

# 7.13. Inspector Functions

The following functions return information about the specified event at the time they are called.

Prototype:	Functional value:
char* event_name(EVENT e)	pointer to name of event
long wait_cnt(EVENT e)	number of processes waiting for event
long queue_ant(EVENT e)	number of processes queued of event
long event_qlen(EVENT e)	sum of wait_cnt and queue_cnt
long state(EVENT e)	state of event: OCC if occurred or NOT_OCC if not occurred
long num_events	number of events in event_set
long event_set_count	number of set operations
double event_queue_sum	sum of queue queue lengths
double event_wait_sum	sum of wait queue lengths
long event_queue_delay_	_count number of queue delays
long event_wait_delay_d	count number of wait delays
double event_queue_leng	gth average queue queue length
double event_wait_lengt	th average wait queue length
double event_queue_time	average queue queue time
<pre>double event_wait_time</pre>	average wait queue time
long event_queue_count	number of queue operations

long event\_wait\_count number of wait operations

#### 7.14. Status Report

The *status\_events* function prints a report of the status of all events in the model.

Prototype: void status\_events(void)

**Example:** status\_events();

For each event, the report includes its state, the number of processes waiting for it, the number of processes queued for it, the name and id of all waiting processes, and the name and id of all queued processes. The report is written to the default output stream or the stream specified in the last call to <code>set\_output\_file</code>.

#### 7.15. Built-In Events

A process can suspend itself until there are no other active processes by waiting on the built-in event *event list empty*.

**Example:** wait(event\_list\_empty);

This event is automatically set by CSIM when all processes have terminated or are waiting for something (e.g., a facility or storage). Modelers sometimes use this to force the initial (sim) process to wait until all work in the system being modeled has completed. Upon being reactivated, the initial process might then produce reports.

### 7. Events

If run length control is involved for a table, qtable, meter or box, (see 14.3), a process can suspend itself until the run length control mechanism signals the end of a run. This is done by waiting for the built-in event *converged*.

**Example:** wait(converged);

# 8. Mailboxes

A mailbox allows for the asynchronous exchange of data between CSIM processes. Any process may send a message to any mailbox, and any process may attempt to receive a message from any mailbox.

A mailbox is comprised of two FIFO queues: a queue of unreceived messages and a queue of waiting processes. At least one of the queues will be empty at any time. When a process sends a message, the message is given to a waiting process (if one exists) or it is placed in the message queue. When a process attempts to receive a message, it is either given a message from the message queue (if one exists) or it is added to the queue of waiting processes.

A message can be either a single long integer or a pointer to some other data object. If a process sends a pointer, it is the responsibility of that process to maintain the integrity of the referenced data until it is received and processed.

# 8.1. Declaring and Initializing a Mailbox

A mailbox is declared in a CSIM program using the built-in type MBOX.

**Example:** MBOX m;

### 8. Mailboxes

Before a mailbox can be used, it must be initialized by calling the *mailbox* function.

Prototype: MBOX mailbox(char\* name)
Example: m = mailbox("requests");

A newly created mailbox contains no messages. The mailbox name is used only to identify the mailbox in output reports and trace messages.

A mailbox that is initialized in the first CSIM process (sim) exists during the entire simulation run and is called a global mailbox. A mailbox initialized in any other process is called a local mailbox. A local mailbox is deleted when the process in which it was initialized terminates.

# 8.2. Sending a Message

A process sends a message by calling the send function.

Prototype: void send(MBOX m, long message)

**Example:** send(m, (long) buffer);

If one or more processes are waiting on this mailbox, the process at the head of the process queue will resume execution and will be given this message. If no processes are waiting, this message will be appended to the tail of the message queue. No simulation time passes during this function call.

A process can also send a message and then suspend until the message is received by another process; this is called a synchronous send operation:

**Prototype:** void synchronous\_send(MBOX m, long message)

**Example:** synchronous\_send(m, (long) buffer);

# 8.3. Receiving a Message

A process receives a message by calling the *receive* function.

Prototype: void receive(MBOX m, long\* message)

**Example:** receive(m,(long\*) &ptr);

If one or more messages are queued at this mailbox, the calling process is given the message at the head of the queue and continues executing. If no messages are queued, the process is suspended from further execution and is added to the tail of the process queue for this mailbox.

# 8.4. Receiving a Message with a Time-Out

Sometimes a process must not wait indefinitely to receive a message. If a process calls the *timed\_receive* function, it will be suspended until either a message is received or the specified amount of time has passed.

### 8. Mailboxes

```
Example: result = timed_receive(m,(long*) &ptr,
100.0);
    if (result ! = TIMED OUT) ...
```

The calling process can check the functional value to determine the circumstances under which it was resumed. If the value EVENT\_OCCURRED is returned, the process was activated because a message was received; if the value TIMED\_OUT is returned, the specified amount of time passed without the process being activated by the receipt of a message.

# 8.5. Synchronous\_send

A process can also send a message with a synchronous send operation (as opposed to a normal send operation as described above). With a synchronous send, the send process waits until the sent message has been received by another process.

**Prototype:** void synchronous\_send(MBOX mb, long message)

**Example:** synchronous\_send(mb, msg,);

# 8.6. Synchronous\_send with a Time-out

A process can also do a synchronous\_send operation with a timeout interval:

**Prototype:** long timed\_synchronous\_send(MBOX mb, long message, double timeout)

**Example:** result = timed\_synchronous\_send (mb, msg,

100.0); if (result ! = TIMED OUT)

The calling process can check the functional value to determine the circumstances under which it was resumed. If the value EVENT\_OCCURRED is returned, the process was activated because a message was received; if the value TIMED\_OUT is returned, the specified amount of time passed without the process being activated by the receipt of a message by another process .

# 8.7. Collecting and Reporting Statistics for Mailboxes

A set of statistics on the usage can be collected for specified mailboxes. Statistics collection for a mailbox is initiated by executing the mailbox\_monitor statement.

Prototype: void mailbox\_monitor(MBOX mb)

**Example:** mailbox\_monitor(mb);

The standard report function automatically proceeds to "print" a report for each monitored mailbox. This report is as follows:

### 8. Mailboxes

### MAILBOX SUMMARY

mailbox name	number of proc visits	•	•	number of messages	message qlength	message rspTime	
- mb	100	0.18737	0.32295	100	1.03091	1.79461	

A report for all of the monitored mailboxes can be generated as follows:

Prototype: void report\_mailboxes()

Example: report\_mailboxes();

# 8.8. Resetting a Mailbox

In some cases, it is necessary to reset the statistics counters for a specific mailbox.

Prototype: void reset\_mailbox(MBOX mb)

**Example:** reset\_mailbox(mb);

Executing this statement does not affect the state of the mailbox. The "reset" and the reset\_mailboxes statements each call reset\_mailbox() for all mailboxes in the model.

All of the events in an mailbox\_set (see below) can be monitored as well.

Prototype: void mailbox\_set\_monitor(MBOX mbs[])

**Example:** mailbox set monitor(mbs);

### 8.9. Mailbox Sets

A mailbox set is an array of related mailboxes for which some special operations are provided. A mailbox set is declared using the C array construct.

```
Example: MBOX mb_set[10];
```

All mailboxes in a mailbox set are initialized with a single call to the *mailbox\_set* function.

```
Example: mailbox_set(mb_set, "mboxes", 10);
```

As with any C array, the mailboxes in an mailbox set are indexed from 0 to num\_mailboxes - 1. Individual mailboxes in the mailbox set can be manipulated using any of normal mailbox functions (e.g., send, and receive).

```
Example: send(mb_set[3], 1);
```

A process can wait for the occurrence of any mailbox in an mailbox set by calling the *recieve\_any* function.

```
Prototype: long receive_any(MBOX mb_set[], (long*) msg)
```

```
Example: mb_index = receive_any(mb_set, &m);
```

This function returns the index of the mailboxthat caused the calling process to proceed. If multiple mailboxes in the set have received messages, the lowest numbered mailbox is the one recognized by the calling process.

A process can also do a timed\_receive\_any() operation at an mailbox set.

### 8. Mailboxes

```
Example: result = time_receive_any(mb_set, &m);
    if(result != TIMED OUT) . . .
```

If the result is not equal to TIMED\_OUT, then it is the index of the mailbox which received the message and caused the process to continue.

An entire mailbox set is deleted by calling the *delete\_mailboxt\_set* function.

```
Prototype: void delete_mailbox_set(MBOX mb_set[])
```

**Example:** delete\_mailbox\_set(mb\_set);

The *delete\_mailbox* function must not be called on individual members of an mailbox set.

# 8.10. Renaming a Mailbox

The name of a mailbox can be changed at any time using the set\_name\_mailbox function.

```
Prototype: void set_name_mailbox(MBOX m, char
*new_name)
```

**Example:** set\_name\_mailbox(m, "responses");

Only the first ten characters of the mailbox's name are stored.

# 8.11. Deleting a Mailbox

When a mailbox is no longer needed, its storage can be reclaimed using the *delete\_mailbox* function.

Prototype: void delete\_mailbox(MBOX m)

**Example:** delete\_mailbox(m);

If a mailbox is local, only the process that created the mailbox can delete it. Once a mailbox has been deleted, it must not be further referenced. Deleting a mailbox causes any unreceived messages to be lost. It is an error to attempt to delete a mailbox on which processes are waiting.

# 8.12. Inspector Functions

The following functions return information about the specified mailbox at the time they are called.

Prototype:	Functional value:
char* mailbox_name (MBOX m)	pointer to name of mailbox
long msg_cnt (MBOX m)	if positive, number of unreceived messages; if negative, magnitude is number of waiting processes
long mailbox_queue_cnt mailbox	number of processes queued at
long mailbox_set_num_msgs	number of messages in a mailbox set
double mailbox_proc_sum	sum of process queue lengths

### 8. Mailboxes

long mailbox\_proc\_delay\_count number of processes delayed long mailbox proc count number of process receiving messages double mailbox\_proc\_length average process queue length double mailbox\_proc\_time average process delay time double mailbox msq sum sum of message queue lengths long mailbox\_msg\_delay\_count number of messages delayed long mailbox\_msg\_count number of messages sent average message queue length double mailbox\_msq\_length average message delay time double mailbox\_msg\_time

# 8.13. Status Report

The *status\_mailboxes* function prints a report of the status of all mailboxes in the model.

Prototype: void status\_mailboxes(void)

**Example:** status\_mailboxes();

For each mailbox, the report includes the number of unreceived messages, the number of waiting processes, and the name and id of all waiting processes. The report is written to the default output stream or the stream specified in the last call to  $set\_output\_file$ .

Each of the CSIM objects (facilities, storages, buffers, events and mailboxes) consists of one or more queues (for suspended processes) and some other structure (servers in a facility, a list of messages in a mailbox, etc.). In some models, it is necessary to be able to manipulate the processes in one of these queues. The queue management features are used to accomplish this.

### 9.1. Process Pointers and Process Structures

The structure for manipulating processes is a PROCESS\_PTR:

**Example:** PROCESS\_PTR ptr

This is the object returned when a process is requested from a CSIM object.

A PROCESS\_PTR object can be used to query the state of a process and to change attributes of a process.

Prototype: long get\_process\_priorty(PROCESS\_PTR pptr)

**Example:** priority = get\_process\_priority(pptr);

**Prototype:** void set\_process\_priorty(PROCESS\_PTR pptr,

long prty)

**Example:** set\_process\_priority(pptr, 5);

Prototype: long get\_process\_identity(PROCESS\_PTR pptr)

**Example:** id = get\_process\_identity(pptr);

**Prototype:** char\* get\_process\_name(PROCESS\_PTR pptr)

**Example:** id = get\_process\_identity(pptr);

A process can retrieve its own process pointer.

**Prototype:** PROCESS\_PTR this\_process(void)

**Example:** pptr = process ptr();

A process can retrieve the next process from a list of processes

**Prototype:** PROCESS PTR next process(PROCESS PTR pptr)

**Example:** p = next\_process(pptr);

A process can have its own user-defined structure. This structure can be established by a process and be retrieved and examined by this process and other processes using a process pointer.

Prototype: void\* get\_this\_struct(void)

**Example:** strct = get\_this\_struct();

A process can establish its own private structure.

Prototype: void set\_this\_struct(void \*strct)

**Example:** set\_this\_struct(strct);

A process can retrieve a pointer to the private structure for another process

Prototype: void\* get\_process\_struct(PROCESS\_PTR pptr)

**Example:** strctr = get\_process\_struct(pptr);

A process can set a private structure for another process.

Prototype: void set\_process\_struct(PROCESS\_PTR pptr,

void\* strctr)

**Example:** set\_process\_struct(pptr, strctr);

# 9.2. Process Queues at Facilities

The queue of processes at a facility can be managed by a set of routines.

The pointer to the first process (the process at the head of the queue) can be retrieved as follows:

**Example:** pptr = facility first process(f);

The pointer to the last process at the end of the queue (the process at the tail of the queue) can be retrieved as follows:

**Example:** pptr = facility\_last\_process(f);

A specific process can be removed from a facility queue as follows:

**Example:** pptr = facility\_remove\_process(f, ppptr);

A process can be placed in a facility queue; the position of this process is determined by its priority relative to the other processes in the queue.

**Prototype:** void facility\_insert\_process(FACILITY f,

PROCESS\_PTR pptr)

**Example:** facility\_insert\_process(f, pptr);

A process can discover if it is occupying a server at a facility:

Prototype: long in\_this\_facility(FACILITY f, long id)

**Example:** n = in\_this\_facility(f, identity());

This function returns true (not zero) if the process with the specified identity occupies one of the servers at the facility designated by f; this function returns false (zero) if the process does not occupy one of the servers at the facility designated by f.

# 9.3. Process Queues at Storages

The routines for managing processes in a storage queue are as follows:

The pointer to the first process (the process at the head of the queue) can be retrieved as follows:

**Prototype:** PROCESS\_PTR storage\_first\_process(STORE s)

**Example:** pptr = storage \_first\_process(s);

The pointer to the last process at the end of the queue (the process at the tail of the queue) can be retrieved as follows:

**Prototype:** PROCESS\_PTR storage\_last\_process(STORE s)

**Example:** pptr = storage\_last\_process(s);

A specific process can be removed from a storage queue as follows:

**Prototype:** PROCESS\_PTR storage\_remove\_process(STORE s,

PROCESS\_PTR pptr)

**Example:** pptr = storage\_remove\_process(s, ppptr);

A process can be placed in a storage queue; the position of this process is determined by its priority relative to the other processes in the queue.

Prototype: void storage\_insert\_process(STORE s,

PROCESS\_PTR pptr)

**Example:** storage\_insert\_process(s, pptr);

### 9.4. Process Queues at Buffers

A buffer has two queues of processes: the queue of processes waiting for a put operation to complete and the queue of processes waiting for a get operation to complete. These two queues are referred to as the put-queue and the get-queue respectively.

The pointer to the first process of the put-queue (the process at the head of the put-queue) can be retrieved as follows:

**Prototype:** PROCESS\_PTR buffer\_put\_first\_process(BUFFER b)

**Example:** pptr = buffer\_put\_first\_process(b);

The pointer to the last process at the end of the put-queue (the process at the tail of the put-queue) can be retrieved as follows:

Prototype: PROCESS\_PTR buffer\_put\_last\_process(BUFFER b)

**Example:** pptr = buffer\_put\_last\_process(b);

A specific process can be removed from a put-queue queue as follows:

**Prototype:** PROCESS\_PTR buffer\_put\_remove\_process(BUFFER

b, PROCESS\_PTR pptr)

**Example:** pptr = buffer\_put\_remove\_process(b, ppptr);

A process can be placed in a buffer put-queue; the position of this process is determined by its priority relative to the other processes in the queue.

**Example:** buffer\_put\_insert\_process(b, pptr);

The pointer to the first process of the get-queue (the process at the head of the put-queue) can be retrieved as follows:

**Prototype:** PROCESS\_PTR buffer\_get\_first\_process(BUFFER

b)

**Example:** pptr = buffer\_get\_first\_process(b);

The pointer to the last process at the end of the get-queue (the process at the tail of the get-queue) can be retrieved as follows:

**Prototype:** PROCESS\_PTR buffer\_get\_last\_process(BUFFER

b)

**Example:** pptr = buffer\_get\_last\_process(b);

A specific process can be removed from a get-queue as follows:

Prototype: PROCESS\_PTR buffer\_get\_remove\_process(BUFFER

b, PROCESS\_PTR pptr)

**Example:** pptr = buffer\_get\_remove\_process(b, ppptr);

A process can be placed in a buffer get-queue; the position of this process is determined by its priority relative to the other processes in the queue.

**Prototype:** void buffer\_get\_insert\_process(BUFFER b,

PROCESS\_PTR pptr)

**Example:** buffer\_get\_insert\_process(b, pptr);

### 9.5. Process Queues at Events

An event has two queues of processes: the queue of processes doing a wait operation and the queue of processes doing a queue operation. These two queues are referred to as the wait-queue and the queue-queue respectively.

The pointer to the first process of the wait-queue (the process at the head of the wait-queue) can be retrieved as follows:

```
Example: pptr = event_first_wait_process(e);
```

The pointer to the last process at the end of the wait-queue (the process at the tail of the wait-queue) can be retrieved as follows:

```
Prototype: PROCESS_PTR event_last_wait_process(EVENT e)
```

```
Example: pptr = event_last_wait_process(e);
```

A specific process can be removed from a wait-queue queue as follows:

```
PROCESS_PTR pptr)
```

```
Example: pptr = event_remove_wait_process(e, ppptr);
```

A process can be placed in an event wait-queue; the position of this process is determined by its priority relative to the other processes in the queue.

```
Example: event_insert_wait_process(e, pptr);
```

The pointer to the first process of the queue-queue (the process at the head of the queue-queue) can be retrieved as follows:

**Prototype:** PROCESS\_PTR event\_first\_queuue\_process(EVENT e)

**Example:** pptr = event\_first\_queuue\_process(e);

The pointer to the last process at the end of the queue-queue (the process at the tail of the queue-queue) can be retrieved as follows:

**Prototype:** PROCESS\_PTR event\_last\_queue\_process(EVENT e)

**Example:** pptr = event\_last\_queue\_process(e);

A specific process can be removed from a queue-queue as follows:

**Prototype:** PROCESS\_PTR event\_remove\_queue\_process(EVENT

e, PROCESS\_PTR pptr)

**Example:** pptr = event\_remove\_queue\_process(e, ppptr);

A process can be placed in a queue-queue; the position of this process is determined by its priority relative to the other processes in the queue.

**Example:** event\_insert\_queue\_process(e, pptr);

# 9.6. Process Queues and Message Lists at Mailboxes

A CSIM mailbox consists of queue of processes waiting to receive messages and a list of messages waiting to be received by processes.

The pointer to the first process of the process queue at a mailbox (the process at the head of the process-queue) can be retrieved as follows:

Prototype: PROCESS\_PTR mailbox\_first\_process(MBOX mb)

**Example:** pptr = mailbox\_first\_process(mb);

The pointer to the last process at the end of the process queue at a mailbox (the process at the tail of the process queue) can be retrieved as follows:

Prototype: PROCESS\_PTR mailbox\_last\_process(MBOX mb)

**Example:** pptr = mailbox\_last\_process (mb);

A specific process can be removed from the process-queue at a mailbox as follows:

**Example:** pptr = mailbox\_remove\_process(mb, ppptr);

A process can be placed in the process queue at a mailbox; the position of this process is determined by its priority relative to the other processes in the queue.

**Example:** mailbox\_insert\_process(mb, pptr);

There is a pointer to a message pointer:

**Example:** MSG\_PTR msg\_ptr;

The pointer to the first message of the message list at a mailbox can be retrieved as follows:

**Prototype:** MSG\_PTR mailbox\_first\_msg(MBOX mb)

**Example:** mptr = mailbox\_first\_msg(mb);

The pointer to the last message at the end of the message list at a mailbox can be retrieved as follows:

**Prototype:** MSG\_PTR mailbox\_last\_msg(MBOX mb)

**Example:** mptr = mailbox last msq(mb);

A specific message can be removed from the message list at a mailbox as follows:

**Prototype:** MSG\_PTR mailbox\_remove\_message(MBOX mb,

MSG\_PTR mptr)

**Example:** mptr = mailbox\_remove\_message(mb, mptr);

A message can be placed in the message list at a mailbox; the position of this message is at the end of the message list.

**Prototype:** void mailbox\_insert\_message(MBOX mb,

MSG\_PTR mptr)

**Example:** mailbox\_insert\_message(mb, mptr);

The next message in a list of messages can be accessed as follows:

**Prototype:** MSG\_PTR next\_msg(MSG\_PTR mptr)

**Example:** mptr = next\_msg(mptr);

The contents of a message can be examined as follows:

**Prototype:** long msg content(MSG PTR mptr)

**Example:** msg = msg\_content(mptr);

# 10. Introduction to Statistics Gathering

CSIM automatically gathers and reports performance statistics for certain types of model components, including facilities and storages. CSIM also provides four general-purpose statistics gathering tools: *tables, qtables, meters*, and *boxes*. These tools can be used for the following purposes:

- to obtain statistics other than mean values for facilities and storages
- to obtain statistics for other model components, such as mailboxes and events
- to obtain statistics for selected submodels or for the model considered as a whole
- to employ the run length control algorithms provided with CSIM (see section 16.3, "Run Length Control")

Any statistics can of course be gathered by declaring and updating variables in a CSIM program. But, the statistics gathering tools are powerful and comprehensive, and their use will decrease the likelihood of programming errors that lead to incorrect statistics. Formatted reports of the statistics gathered with these tools can easily be included in the model output.

The following steps are suggested for adding statistics gathering to a model:

- Identify what statistics are of interest and which statistics gathering tools are appropriate.
- Declare a global pointer (variable) for each statistics gathering tool that will be used.

### 10. Introduction to Statistics Gathering

- Initialize each statistics gathering tool, usually at the beginning of the *sim* function.
- Add instrumentation (*i.e.*, function calls) to the model to feed data to the tools.
- Generate reports by calling the *report* function.

The magnitudes of the performance statistics obviously depend on the time unit that is chosen for the model. Most of the reports produced by the statistics gathering tools will accommodate floating point numbers with six digits to the left of the decimal point and six digits to the right of the decimal point. Up to nine digits can be displayed for integer values. The time unit should be chosen to avoid performance values so far from unity that digits of interest are not displayed.

# 11. Tables

A table is used to gather statistics on a sequence of discrete values such as interarrival times, service times, or response times. Data values are "recorded" in a table to include them in the statistics. A table does not actually store the recorded values; it simply updates the statistics each time a value is included. (See section 11.6, "Moving Windows", for the only exception to this rule.)

The statistics maintained by a table include the minimum, maximum, range, mean, variance, standard deviation, and coefficient of variation. Optional features for a table allow the creation of a histogram, the calculation of confidence intervals, and the computation of statistics for values in a moving window.

First-time users of tables should focus on the following three sections, which explain how to set up tables, record values, and produce reports. Subsequent sections describe the more advanced features of tables.

### 11. Tables

# 11.1. Declaring and Initializing a Table

A table is declared in a CSIM program using the built-in type TABLE.

**Example:** TABLE t;

Before a table can be used, it must be initialized by calling the *table* function.

**Prototype:** TABLE table (char\* name);

**Example:** t = table ("response times");

The table name is used only to identify the table in the output reports. Up to 80 characters in the name will be stored by CSIM. A newly created table contains no values and all the statistics are zero.

A table can be initialized as a permanent table using the *permanent\_table* function.

**Prototype:** TABLE permanent\_table (char\* name)

**Example:** t = permanent\_table ("response times");

The information in a permanent table is not cleared when the *reset* function is called, and a permanent table is not deleted when *rerun* is called. In all other ways, a permanent table is exactly like any other table. Permanent tables are often used to gather data across multiple runs of a model. As a general rule, do not make a table permanent unless you have a specific reason for doing so.

# 11.2. Tabulating Values

A value is included in a table using the *tabulate* function.

**Prototype:** void tabulate(TABLE t, double value)

**Example:** tabulate(t, 1.0);

Tables are designed to maintain statistics on data of type double. Data of other types, such as integer, must be cast to type double in the call to record.

Earlier versions of CSIM used an alternative statement to accomplish this function:

**Prototype:** void record(double value, TABLE t)

**Example:** record(1.0, t);

Caution: It is a common mistake to reverse the order of the parameters in calls to *record*. Think of "recording the value *x* in table *t*".

# 11.3. Producing Reports

Reports for tables are most often produced by calling the *report* function, which prints reports for all statistics gathering objects. A report can be generated for a specified table at any time by calling the *report\_table* function.

Prototype: void report\_table(TABLE t)

**Example:** report\_table(t);

### 11. Tables

Reports can be produced for all existing tables by calling the *report tables* function.

**Prototype:** void report\_tables(void)

**Example:** report\_tables();

The report for a table will include the table name and all statistics, as illustrated below. If the table is empty, a message to that effect is printed instead of the statistics.

TABLE 1: response	times		
minimum	0.009880	mean	2.881970
maximum	13.702809	variance	7.002668
range	13.692929	standard deviation	2.646255
observations	962	coefficient of var	0.918211

A summary report for all tables can be generated by calling the *table\_summary* function.

**Prototype:** void table\_summary(void)

**Example:** table\_summary();

The report that is produced contains one line for each table and includes only a subset of the statistics. If a table is empty, no statistics will appear in the last three columns.

TABLE SUMMARY				
standard name	observations	mean	maximum	deviation
response times	962	2.881970	13.702809	2.646255

# 11.4. Histograms

A histogram can be specified for a table in order to obtain more detailed information about the recorded values. The mode and other percentiles can often be estimated from a histogram. A histogram is specified for a table by calling the *table\_histogram* function.

**Prototype:** void table\_histogram(TABLE t, long nbucket,

double min, double max)

**Example:** table\_histogram(t, 10, 0.0, 10.0);

The number of buckets in the histogram will be *nbucket*. The smallest value in the first bucket will be *min*; the largest value in the last bucket will be *max*. All buckets will have the same width of (*max-min*)/*nbucket*. An underflow bucket and an overflow bucket will automatically be created if needed to hold values less than *min* or greater than *max*.

Usually, a histogram is specified for a table immediately after the table is initialized. Additional calls can be made to *table\_histogram* to change the characteristics of the histogram, but only if the table is empty.

A report for a table having a histogram will include an additional section as illustrated below. For each bucket in the histogram, the following information will be displayed: the smallest value the bucket can hold, the number of values in the bucket, the proportion of all values that are in the bucket, the proportion of all values in the bucket and all preceding buckets, and a bar whose length corresponds to the proportion of values in the bucket.

### 11. Tables

			cumulative
lower limit	frequency	proportion	proportion
0.00000	265	0.275468	0.275468 ************
1.00000	219	0.227651	0.503119 ************
2.00000	125	0.129938	0.633056 *******
3.00000	92	0.095634	0.728690 ******
4.00000	74	0.076923	0.805613 ******
5.00000	54	0.056133	0.861746 ****
6.00000	53	0.055094	0.916840 ****
7.00000	38	0.039501	0.956341 ***
8.00000	8	0.008316	0.964657 *
9.00000	8	0.008316	0.972973 *
 >=10.00000	26	0.027027	1.000000 **

If leading or trailing buckets contain no values, the lines in the report for these buckets will not be printed. This allows the histogram to be output as compactly as possible without losing any information.

CSIM must save information for each bucket in a histogram. Consequently, the storage requirements for a table that has a histogram are proportional to the number of buckets.

# 11.5. Confidence Intervals

CSIM can automatically compute confidence intervals for the mean of the data in any table. The confidence interval calculations are enabled by calling the *table\_confidence* function.

**Prototype:** void table\_confidence(TABLE t)

**Example:** table confidence(t);

If confidence intervals have been requested, the report for a table will have an additional section, as illustrated below.

confidence intervals for the mean after 50000 observations				
level	confidence interval	rel. error		
90 %	4.114119 +/- 0.296434 = [3.817684, 4.410553]	0.077648		
95 %	4.114119 +/- 0.354041 = [3.760078, 4.468159]	0.078837		
98 %	4.114119 +/- 0.421555 = [3.692563, 4.535674]	0.080279		

Chapter 16, "Confidence Intervals and Run Length Control" describes confidence intervals in detail and explains how to interpret the information in this report.

# 11.6. Moving Windows

By default, all values recorded in a table are included in the statistics. If a moving window is specified for a table, only the last *n* values are used in computing the statistics, where *n* is called the window size. A moving window is specified for a table using the *table\_moving\_window* function.

**Prototype:** void table moving window(TABLE t, long n)

**Example:** table\_moving\_window(t, 1000);

Usually, a table's moving window is specified immediately after the table is initialized. Additional calls can be made to *table\_moving\_window* to change the table's window size. It is an error to specify a moving window for a table that is not empty.

If a table has a window size of *n*, the last *n* values recorded in the table must be saved by CSIM. Consequently, the storage requirements for a table having a moving window are proportional to its window size.

### 11. Tables

# 11.7. Inspector Functions

All statistics maintained by a table can be retrieved during the execution of a model or upon its completion. The attributes of a table (*i.e.*, its name and moving window size) can also be retrieved.

### Prototype:

# char\* table\_name(TABLE t) long table\_window\_size(TABLE t) long table\_cnt(TABLE t) double table\_min(TABLE t) double table\_max(TABLE t) double table\_sum(TABLE t) double table\_sum\_square(TABLE t) double table\_mean(TABLE t) double table\_range(TABLE t) double table\_var(TABLE t) double table\_var(TABLE t) double table\_stddev(TABLE t) double table\_stddev(TABLE t)

## Functional value:

pointer to name of table
size of moving window
number of values recorded
minimum value
maximum value
sum of values
sum of squares of values
mean of values
range of values
variance of values
standard deviation of values
coefficient of variation of
values

The following inspector functions retrieve information about the confidence interval associated with a table:

Prototype:	Functional Value:
double table_conf_halfwidth(double level, TABLE t)	halfwidth
double table_conf_lower(double level, TABLE t)	lower end
double table_conf_upper(double level, TABLE t)	upper end

The following inspector functions retrieve information about the run length control associated with a table:

Prototype:	Functional Value:
long table_batch_size(TABLE t)	current size of batch
long table_batch_count(TABLE t)	number of batches used
long table_converged(TABLE t)	TRUE or FALSE
double table_conf_mean(TABLE t)	mid point of conf. int.
double table conf accuracy(double level, TABLE	t) accuracy achieved

Although most statistics are mathematically undefined if there is no data, the corresponding inspector functions return a value of zero if the table is empty.

### 11. Tables

The following inspector functions retrieve information about the histogram associated with a table.

Prototype:	Functional value:
long table_histogram_num(TABLE t)	number of buckets
double table_histogram_low(TABLE t)	smallest value that is not underflow
double table_histogram_high(TABLE t)	largest value that is not overflow
double table_histogram_width(TABLE t)	width of each bucket
long table_histogram_bucket(TARLE t,long i)	number of values in bucket
long taable_histogram_total(TABLE t)	number of values in all buckets

The number of buckets in a histogram does not include the underflow or overflow buckets. Bucket number 0 is the underflow bucket; bucket number  $1+table\_histogram\_num()$  is the overflow bucket. If a histogram has not been specified for a table, the above inspector functions all return zero values.

The inspector functions that retrieve information about the results of run-length control are described in section 16.3.

# 11.8. Renaming a Table

The name of a table can be changed at any time using the set\_name\_table function.

**Prototype:** void set\_name\_table(TABLE t, char\* new\_name)

**Example:** set\_name\_table(t, "elapsed time");

Only the first 80 characters of the table's name are stored.

# 11.9. Resetting a Table

Resetting a table causes all information maintained by the table to be reinitialized. All optional features selected for the table (*e.g.*, histogram, confidence intervals, moving window) remain in effect and are also reinitialized.

The *reset* function is usually used to reset all statistics gathering tools at once. A specific table can be reset using the *reset\_table* function.

**Prototype:** void reset table(TABLE t)

**Example:** reset\_table(t);

Although permanent tables are not reset by the *reset* function, they can be reset explicitly by calling *reset\_table*.

### 11. Tables

# 11.10. Deleting a Table

When a table is no longer needed, its storage can be reclaimed using the *delete\_table* function.

Prototype: void delete\_table(TABLE t)

**Example:** delete\_table(t);

Once a table has been deleted, it must not be further referenced. If enhancements (either histogram, confidence intervals, or moving window) have been defined for a table, the each of these enhancements is also deleted when the corresponding table is deleted.

# 12. Qtables and Qtable\_Dbl's

A qtable is used to gather statistics on an integer-valued function of time, such as the length of a queue, the population of a subsystem, or the number of available resources. Every change in the value of the function must be "noted" by calling a CSIM function. A qtable does not actually save the functional values; it simply updates the statistics each time the value changes. (See section 12.6 for the only exception to this rule.)

A qtable\_dbl is used to gather statistics on a real-valued (double) function of time. Every change in the value of the function is noted by calling a CSIM function. A qtable\_dbl is a qtable structure; values of the function are entered using the record\_value() procedure. A qtable becomes a qtable\_dbl when a double value is recorded in it (using the record\_value() function).

The statistics maintained by a qtable and a qtable\_dbl include the minimum, maximum, range, mean, variance, standard deviation, and coefficient of variation. The number of changes in the functional value is maintained, as well as the initial and final values. Optional features for a qtable allow the creation of a histogram, the calculation of confidence intervals, and the computation of statistics for values in a moving window.

First-time users of qtables should focus on the following three sections, which explain how to set up qtables, note changes in their values, and produce reports. Subsequent sections describe the more advanced features of qtables.

## 12.1. Declaring and Initializing a Qtable

A qtable is declared in a CSIM program using the built-in type QTABLE.

**Example:** QTABLE qt;

Before a qtable can be used, it must be initialized by calling the *qtable* function.

**Prototype:** QTABLE qtable(char\* name)

**Example:** qt = qtable("queue length");

The qtable name is used only to identify the qtable in the output reports. Up to 80 characters in the name will be stored by CSIM. A newly created qtable has an initial value of zero. To create a qtable with a non-zero initial value, call the *note\_state* function (described below) immediately after creating the qtable.

A qtable can be initialized as a permanent qtable using the *permanent\_qtable* function.

**Prototype:** QTABLE permanent\_qtable(char\* name)

**Example:** qt = permanent-qtable("queue length");

## 12.2. Noting a Change in Value

The most common way for the value of a qtable to change is for it to increase or decrease by one. Such a change would occur when a customer joins a queue or a resource is allocated. The value of a qtable is increased by one using the *note\_entry* function.

**Prototype:** void note\_entry(QTABLE qt)

**Example:** note\_entry(qt);

The value of a qtable is decreased by one using the *note\_exit* function.

Prototype: void note\_exit(QTABLE qt)

**Example:** note\_exit(qt);

The value of a qtable can be changed to an arbitrary integer-valued number using the *note\_value* function.

**Prototype:** void note\_value(QTABLE qt, long value)

**Example:** note\_value(qt, 12);

The value of a qtable\_dbl can be changed to an arbitrary floating (double) number using the *record\_value* function.

**Prototype:** void record\_value (QTABLE qt, double fvalue)

**Example:** record\_value(qt, 1.75);

The value of a qtable\_dbl can be initialized to an arbitrary floating (double) number using the set\_initial\_value function.

**Prototype:** void set\_initial\_value(QTABLE qt,

double fvalue)

**Example:** set\_initial\_value(qt, -1.0);

Note: a qtable becomes a qtable\_dbl when a record\_value() or a set\_initial\_value() operation is executed. Using *note\_value* and *record\_value* operations on the same qtable is incorrect.

## 12.3. Producing Reports

Reports for qtables are most often produced by calling the *report* function, which prints reports for all statistics gathering objects. A report can be generated for a specified qtable at any time by calling the *report\_qtable* function.

**Prototype:** void report qtable(QTABLE qt)

**Example:** report\_qtable(qt);

Reports can be produced for all existing qtables by calling the *report qtables* function.

**Prototype:** void report\_qtables(void)

**Example:** report\_qtables();

The report for a qtable will include the qtable name and all statistics, as illustrated below. If no time has passed since the creation or reset of the qtable, a message to that effect is printed instead of the statistics.

QTABLE 1:	queue	length			
initial final entries exits	0 4 966 962	minimum maximum range	0 14 14	mean variance standard deviation coeff of variation	2.788416 8.529951 2.920608 1.047408

A summary report for all qtables can be generated by calling the *qtable summary* function.

**Prototype:** void qtable\_summary(void)

**Example:** qtable\_summary();

The report that is produced contains one line for each qtable and includes only a subset of the statistics. If no time has passed, no statistics will appear in the last three columns.

QTABLE SUMMA	RY				
name	entries	exits	mean	maximum	standard deviation
queue length	966	962	2.788416	14	2.920608

Note: the report and histogram for a qtable\_dbl are similar to the reports for a qtable, except that double values are printed where appropiate.

## 12.4. Histograms

A histogram can be specified for a qtable in order to obtain more detailed information about the functional values. Depending on how the qtable is being used, its histogram might give the distribution of the queue lengths, the subsystem population, or the number of available resources. A histogram is specified for a table by calling the *qtable\_histogram* function.

**Prototype:** void qtable\_histogram(QTABLE qt, long nbucket, long min, long max)

**Example:** qtable histogram(qt, 11, 0, 10);

The number of buckets in the histogram will be (no greater than) *nbucket*. The smallest value in the first bucket will be *min*; the largest value in the last bucket will be *max*. All buckets will have the same width, which will be rounded up to an integer if necessary. An underflow bucket and an overflow bucket will automatically be created if needed to hold values less than *min* or greater than *max*.

Caution: The min and max parameters of qtable\_histogram are of type long, whereas the analogous parameters of table\_histogram are of type double.

Usually, a histogram is specified for a qtable immediately after the qtable is initialized. Additional calls can be made to *qtable\_histogram* to change the characteristics of the histogram, but only if the qtable is empty.

A report for a qtable having a histogram will include an additional section as illustrated below. For each bucket in the histogram, the following information will be displayed: the smallest value the bucket can hold, the total time the functional value was in the bucket, the proportion of time that the functional value was in the bucket, the proportion of all functional values in the bucket and all preceding buckets, and a bar whose length corresponds to the proportion of time the functional value was in the bucket.

			cumulative	
number	total time	proportion	proportion	
0	248.74145	0.249003	0.249003	*******
1	185.45534	0.185651	0.434654	*******
2	157.13503	0.157300	0.591954	******
3	100.01937	0.100125	0.692079	******
4	78.14196	0.078224	0.770303	*****
5	62.59210	0.062658	0.832961	****
6	44.38455	0.044431	0.877392	***
7	35.33308	0.035370	0.912762	***
8	25.94494	0.025972	0.938735	**
9	21.48465	0.021507	0.960242	**

>= 10
-------

If leading or trailing buckets contain no values, the lines in the report for these buckets will not be printed. This allows the histogram to be output as compactly as possible without losing any information.

CSIM must save information for each bucket in a histogram. Consequently, the storage requirements for a qtable that has a histogram are proportional to the number of buckets.

#### 12.5. Confidence Intervals

CSIM can automatically compute confidence intervals for the mean value of any qtable. The confidence interval calculations are enabled by calling the *qtable confidence* function.

**Prototype:** void gtable\_confidence(QTABLE gt)

**Example:** qtable\_confidence(qt);

If confidence intervals have been requested, the report for a qtable will include an additional section, as illustrated below.

confidence intervals for the mean after 29600.000000 time units				
level	confidence interval	rel. error		
90 %	4.319412 +/- 0.491696 = [3.827715, 4.811108]	0.128457		
95 %	4.319412 +/- 0.588209 = [3.731203, 4.907621]	0.157646		
98 %	4.319412 +/- 0.701971 = [3.617441, 5.021382]	0.194052		

Section 16.1, "Confidence Intervals", describes confidence intervals in detail and explains how to interpret the information in this report.

## 12.6. Moving Windows

By default, all changes to the value of a qtable are included in the statistics. If a moving window is specified for a qtable, only the last n changes are used in computing the statistics, where n is called the window size. A moving window is specified for a qtable using the n

**Prototype:** void gtable moving window(QTABLE gt, long n)

**Example:** qtable\_moving\_window(qt, 1000);

Usually, a qtable's moving window is specified immediately after the qtable is initialized. Additional calls can be made to *qtable\_moving\_window* to change the qtable's window size. It is an error to specify a moving window for a qtable that is not empty.

If a qtable has a window size of *n*, the last *n* changes noted for the qtable must be saved by CSIM. Consequently, the storage requirements for a qtable having a moving window are proportional to its window size.

*Note:* In an alternate implementation of moving windows, the window size would be specified as an amount of time. The storage requirements of such an implementation would be non-constant and potentially prohibitive.

## 12.7. Inspector Functions

All statistics maintained by a qtable can be retrieved during the execution of a model or upon its completion. The attributes of a qtable (*i.e.*, its name and moving window size) can also be retrieved.

## Prototype:

## Functional value:

char* qtable_name(QTABLE qt)	pointer to name of qtable
long qtable_window_size(QTABLE qt)	moving window size
long qtable_entries(QTABLE qt)	number of note_entry's
long qtable_exits(QTABLE qt)	number of note_exit's
long qtable_min(QTABLE qt)	minimum value
long qtable_max(QTABLE qt)	maximum value
long qtable_range(QTABLE qt)	range of values
long qtable_initial(QTABLE qt)	initial value
long qtable_current(QTABLE qt)	current value
double qtable_sum(QTABLE qt)	sum of values weighted by time
double qtable_sum_square(QTABLE qt)	sum of squared weighted
double qtable_mean(QTABLE qt)	mean value
double qtable_var(QTABLE qt)	variance of values
double qtable_stddev(QTABLE qt)	standard deviation of values
double qtable_cv(QTABLE qt)	coefficient of variation of values

When a qtable has recorded double values, the following inspector functions should be used (instead of the equivalent functions listed above):

## Prototype:

#### **Functional value:**

double qtable_entries(QTABLE qt)	sum of positive changes
double qtable_dbl_exits(QTABLE qt)	sum of negative changes
double qtable_dbl_range(QTABLE qt)	range of values
double qtable_dbl_min(QTABLE qt)	minimum value
double qtable_dbl_max(QTABLE qt)	maximum value

double qtable\_dbl\_initial(QTABLE qt) initial value double qtable\_dbl\_current(QTABLE qt) current value

The following inspector functions retrieve information about the confidence interval associated with a table:

Prototype: Value:	Functional
double qtable_conf_halfwidth(double level, QTABLE qt)	halfwidth
double qtable_conf_lower(double level, QTABLE qt)	lower end
double qtable_conf_upper(double level, QTABLE qt)	upper end
<b>T</b>	

The following inspector functions retrieve information about the run length control associated with a table:

Prototype:	Functional Value:
long qtable_batch_size(QTABLE qt)	current size of batch
long qtable_batch_count(QTABLE qt)	number of batches used
double qtable_conf_mean(QTABLE qt)	mid point of conf. int.
long qtable_converged(QTABLE qt)	TRUE or FALSE
double qtable_conf_aaccuracy(double level, QIF	ख्राम् ्र्t) accuracy achieved

Many statistics are mathematically undefined if zero time has passed since the creation or reset of a qtable. The corresponding inspector functions return a value of zero in this case.

The following inspector functions retrieve information about the histogram associated with a qtable.

Prototype:	Functional value:
long qtable_histogram_num(QTABLE qt)	number of buckets

double qtable\_histogram\_low(QTABLE qt)

double qtable\_histogram\_high(QTABLE qt)

double qtable\_histogram\_width(QTABLE qt)

largest value that is not overflow

double qtable\_histogram\_width(QTABLE qt)

width of each bucket

larg qtable\_histogram\_bucket (QTABLE qt,larg i)

total time value is in bucket

The number of buckets in a histogram does not include the underflow or overflow buckets. Bucket number 0 is the underflow bucket; bucket number 1+qtable\_histogram\_num() is the overflow bucket. If a histogram has not been specified for a qtable, the above inspector functions all return zero values.

The inspector functions that retrieve information about the results of run-length control are described in section 14.3, "Run Length Control".

## 12.8. Renaming a Qtable

The name of a qtable can be changed at any time using the set\_name\_qtable function.

**Prototype:** void set\_name\_qtable(QTABLE qt, char

\*new\_name)

**Example:** set\_name\_qtable(qt, "number in queue");

Only the first 80 characters of the qtable's name are stored.

## 12.9. Resetting a Qtable

Resetting a qtable causes all information maintained by the qtable to be reinitialized, except that the current value is saved for use in computing future values. All optional features selected for the qtable (e.g., histogram, confidence intervals, moving window) remain in effect and are also reinitialized.

The *reset* function is usually used to reset all statistics gathering tools at once. A specific qtable can be reset using the *reset\_qtable* function.

**Prototype:** void reset\_qtable(QTABLE qt)

**Example:** reset\_qtable(qt);

Although permanent qtables are not reset by the *reset* function, they can be reset explicitly by calling *reset\_qtable*.

## 12.10. Deleting a Qtable

When a qtable is no longer needed, its storage can be reclaimed using the *delete\_qtable* function.

**Prototype:** void delete\_qtable(QTABLE qt)

**Example:** delete\_qtable(qt);

Once a qtable has been deleted, it must not be further referenced.

## 13. Meters

A meter is used to gather statistics on the flow of entities such as customers or resources past a specific point in a model. Meters can be used to measure arrival rates, completion rates, and allocation rates. A meter can be thought of as a probe that is inserted at some point in a model.

While a meter primarily measures the rate at which entities flow past it, a meter also keeps statistics on the times between passages. These interpassage times are recorded in a table, which is an integral part of every meter.

First-time users of meters should focus on the following three sections, which explain how to set up meters, update meters, and produce reports. Subsequent sections describe the more advanced features of meters.

## 13.1. Declaring and Initializing a Meter

A meter is declared in a CSIM program using the built-in type METER.

**Example:** METER m;

#### 13. Meters

Before a meter can be used, it must be initialized by calling the *meter* function.

**Prototype:** METER meter(char\* name)

**Example:** m = meter("system completions");

The meter name is used only to identify the meter in the output reports. Up to 80 characters in the name will be stored by CSIM.

## 13.2. Instrumenting a Model

An entity notes its passage by a meter using the *note\_passage* function.

Prototype: void note\_passage(METER m)

**Example:** note\_passage(m);

For the statistics to be accurate, every entity of interest must note its passage and do so at the correct time.

## 13.3. Producing Reports

Reports for meters are most often produced by calling the *report* function, which prints reports for all statistics gathering objects. A report can be generated for a specified meter at any time by calling the *report\_meter* function.

Prototype: void report\_meter(METER m)

**Example:** report\_meter(m);

Reports can be produced for all existing meters by calling the *report\_meters* function.

Prototype: void report\_meters(void)

**Example:** report\_meters();

The report for a meter, as illustrated below, will include the meter name, the number of passages, the passage rate, and statistics on the interpassage times. If no time has elapsed, a message to that effect is printed instead of the statistics.

METER 2: System completions						
count	494	rate	0.988000			
interpassage ti	me statistics					
minimum	0.001258	mean	1.008764			
maximum	6.533026	variance	0.994894			
range	6.531768	standard deviation	0.997444			
observations	494	coefficient of var	0.988778			

#### 13. Meters

A summary report for all meters can be generated by calling the *meter summary* function.

Prototype: void meter\_summary(void)

**Example:** meter\_summary();

The report that is produced contains one line for each meter and includes only a subset of the statistics. If no time has passed, undefined statistics will be omitted.

METER SUMMARY				
name	passages	rate	mean ip time	max ip time
System arrivals	501	1.002000	0.997048	6.679665
System completions	494	0.988000	1.008764	6.533026

## 13.4. Histograms

A histogram can be specified for the interpassage times of a meter. This is accomplished using the *meter\_histogram* function.

**Prototype:** void meter\_histogram(METER m, long nbucket,

double min, double max)

**Example:** meter\_histogram(m, 10, 0.0, 10.0);

The histogram for a meter is exactly the same as the histogram for a table. See section 11.4, "Histograms", for details.

## 13.5. Confidence Intervals

CSIM can automatically compute confidence intervals for the mean interpassage time at a meter. The confidence interval calculations are enabled by calling the *meter\_confidence* function.

Prototype: void meter\_confidence(METER m)

**Example:** meter\_confidence(m);

The confidence intervals for a meter are the same as the confidence intervals for a table. See section 16.1, "Confidence Intervals", for details.

## 13.6. Moving Windows

Moving windows are not supported by meters.

## 13.7. Inspector Functions

All statistics maintained by a meter can be retrieved during the execution of a model or upon its completion. The name of a meter can also be retrieved.

#### 13. Meters

#### Prototype:

char\* meter\_name (METER m)
double meter\_start\_time (METER m)
long meter\_cnt (METER m)
double meter\_rate (METER m)
TABLE meter\_ip\_table (METER m)

#### **Functional value:**

pointer to name of meter time at which recording began number of passages noted rate of passages pointer to interpassage time table

Although the passage rate is mathematically undefined if no time has passed, the *meter\_rate* function returns the value zero in this case.

The pointer to a meter's interpassage time table can be passed to the inspector functions for a table in order to obtain interpassage time statistics.

**Example:** max\_ip\_time = table\_max(meter\_ip\_table(m));

If no passages have occurred, the interpassage time table is empty. The interpassage time contributed by the first passage is the time from the beginning of the observation period to that first passage.

## 13.8. Renaming a Meter

The name of a meter can be changed at any time using the set\_name\_meter function.

**Prototype:** void set\_name\_meter(METER m, char \*new\_name)

**Example:** set\_name\_meter(m, "system departures");

Only the first 80 characters of the meter's name are stored.

## 13.9. Resetting a Meter

Resetting a meter causes all information maintained by the meter to be reinitialized, except that the time of the last passage is saved for use in computing the next interpassage time. All optional features selected for the meter (e.g., histogram, confidence intervals, moving window) remain in effect and are also reinitialized.

The *reset* function is usually used to reset all statistics gathering tools at once. A specific meter can be reset using the *reset\_meter* function.

Prototype: void reset\_meter(METER m)

Example: reset\_meter(m);

#### 13. Meters

## 13.10. Deleting a Meter

When a meter is no longer needed, its storage can be reclaimed using the *delete\_meter* function.

Prototype: void delete\_meter(METER m)

**Example:** delete\_meter(m);

Once a meter has been deleted, it must not be further referenced.

## 14. Boxes

A box conceptually encloses part or all of a model. The box gathers statistics on the number of entities in the box (*i.e.*, the population) and the amount of time entities spend in the box (*i.e.*, the elapsed time). An entity might be a customer, a message, or a resource. Boxes are usually used to gather statistics on queue lengths, response times, and populations. Instrumenting a model involves inserting function calls at the places that entities enter and exit the box.

A table and a qtable are invisible but integral parts of every box. Statistics on the elapsed times are kept in the table, statistics on the population are kept in the qtable.

First-time users of boxes should focus on the following three sections, which explain how to set up boxes, instrument a model, and produce reports. Subsequent sections describe the more advanced features of boxes.

## 14.1. Declaring and Initializing a Box

A box is declared in a CSIM program using the built-in type BOX.

Example: BOX b;

#### 14. Boxes

Before a box can be used, it must be initialized by calling the *box* function.

Prototype: BOX box(char\* name)
Example: b = box("system");

The box name is used only to identify the box in the output reports. Up to 80 characters in the name will be stored by CSIM. A newly created box is always empty. To create a non-empty box, call the *enter\_box* function (described in the following section) the appropriate number of times immediately after creating the box.

A box can be initialized as a permanent box using the *permanent\_box* function.

Prototype: BOX permanent\_box(char\* name)
Example: b = permanent\_box("system");

The information in a permanent box is not cleared when the *reset* function is called, and a permanent box is not deleted when *rerun* is called. In all other ways, a permanent box is exactly like a box. As a general rule, do not make a box permanent unless you have a specific reason for doing so.

## 14.2. Instrumenting a Model

An entity enters a box by calling the *enter\_box* function.

Prototype: double enter\_box(BOX b)
Example: timestamp = enter box(b);

This function returns a timestamp that must be saved by the entity that entered the box. The entity exits the box by calling the *exit\_box* function and passing to it the timestamp that it received upon entry.

**Prototype:** void exit\_box(BOX b, double entry\_time)

**Example:** exit\_box(b, timestamp);

It is the responsibility of the programmer to ensure that the integrity of the timestamp is maintained while the entity is in the box. Because boxes may be nested or may overlap, it is advisable to make the timestamp local to the CSIM process and to use a separate timestamp variable for each box. An invalid timestamp (*i.e.*, one that is less than zero or greater than the current time) will cause an error.

## 14.3. Producing Reports

Reports for boxes are most often produced by calling the *report* function, which prints reports for all statistics gathering objects. A report can be generated for a specified box at any time by calling the *report\_box* function.

**Prototype:** void report\_box(BOX b)

**Example:** report\_box(b);

Reports can be produced for all existing boxes by calling the *report\_boxes* function.

Prototype: void report\_boxes(void)

**Example:** report\_boxes();

The report for a box, as illustrated below, will include the box name, statistics on the elapsed times, and statistics on the population of

#### 14. Boxes

the box. If the box is empty or no time has passed since its creation or reset, messages to that effect are printed instead of the statistics. Note that statistics on the elapsed times reflect only those entities that have exited the box. Entities still in the box when the report is produced contribute to the population statistics but not to the elapsed time statistics.

BOX 1: Queue statistics								
etatietice on o	Jancod tim	00						
statistics on elapsed times								
minimum		0.009880	9880 mean		2.088345			
maximum 7.9		7.943915	variance		3.211423			
range		7.934035	standard deviation		1.792044			
observations	S	494	coefficient of var		0.858117			
statistics on p	onulation							
statistics on p	opulation							
initial	0	minimum	0	mean				
final	7	maximum	10	variance				
entries	501	range	10	standard deviation	n			
exits	494			coeff of variation				

A summary report for all boxes can be generated by calling the *box\_summary* function.

**Prototype:** void box\_summary(void)

**Example:** box\_summary();

The report that is produced contains one line for each box and includes only a subset of the statistics. If a box is empty or no time has passed since its creation or reset, some statistics will not appear.

BOX SUMMARY				
name	mean elapsed-time	maximum elapsed-time	mean population	maximum population
Queue statistic	2.088345	7.943915	2.093697	10

## 14.4. Histograms

A histogram can be specified for the elapsed times in a box and for the population of a box using the following functions.

**Prototype:** void box\_time\_histogram(BOX b, long nbucket,

double min, double max)

**Example:** box\_time\_histogram(b, 10, 0.0, 10.0);

**Prototype:** void box\_number\_histogram(BOX b, long

nbucket, long min, long max)

**Example:** box\_number\_histogram(b, 10, 0, 10);

The histogram for the elapsed times is the same as the histogram for a table. See section 11.4, "Histograms", for details. The histogram for the population of a box is the same as the histogram for a qtable. See section 12.4, "Histograms", for details.

#### 14. Boxes

Caution: The min and max parameters of box\_time\_histogram are of type double, whereas the corresponding parameters of box\_number\_histogram are of type long.

#### 14.5. Confidence Intervals

Confidence intervals can be requested for the mean of the elapsed times in a box and for the mean population of a box using the following functions.

**Prototype:** void box\_time\_confidence(BOX b)

**Example:** box time confidence(b);

**Prototype:** void box number confidence(BOX b)

**Example:** box number confidence(b);

These two types of confidence intervals are identical to the confidence intervals for a table and qtable, respectively. See sections X.X, "Confidence Intervals", and XX.X, "Confidence Intervals", for details.

## 14.6. Moving Windows

Moving windows can be specified for the elapsed times in a box and for the population of a box using the following functions.

**Prototype:** void box\_time\_moving\_window(BOX b, long n)

**Example:** box\_time\_moving\_window(b, 1000);

**Prototype:** void box\_number\_moving\_window(BOX b, long n)

**Example:** box\_number\_moving\_window(b, 1000);

The window for the elapsed times specifies the number of entities whose elapsed times will be included in the statistics. The window for the population specifies the number of changes in the population that will be included in the statistics. Consequently, the simulation time covered by these two windows may not be the same.

## 14.7. Inspector Functions

All statistics maintained by a box can be retrieved during the execution of a model or upon its completion. The name of a box can also be retrieved.

#### 14. Boxes

#### Prototype:

#### **Functional value:**

char\* box\_name (BOX b) pointer to name of box

TABLE box\_time\_table (BOX b) pointer to elapsed time table

QTABLE box\_number\_qtable (BOX b) pointer to population qtable

The pointer to a box's elapsed time table can be passed to the inspector functions for a table in order to obtain statistics on the times that entities have spent in the box.

**Example:** max\_time\_in\_box = table\_max (box\_time\_table(b));

If no entities have exited the box, the table will be empty and zeros will be returned for the undefined statistics.

The pointer to a box's population qtable can be passed to the inspector functions for a qtable in order to obtain statistics on the population.

**Example:** max\_population = qtable\_max (box\_number\_qtable(b));

If no time has passed, zero values will be returned for the undefined statistics.

## 14.8. Renaming a Box

The name of a box can be changed at any time using the set\_name\_box function.

**Prototype:** void set\_name\_box(BOX b, char \*new\_name)

**Example:** set\_name\_box(b, "system");

Only the first 80 characters of the box's name are stored.

## 14.9. Resetting a Box

Resetting a box causes all information maintained by the box to be reinitialized, except that the number currently present in the box is saved for use in computing future populations. All optional features selected for the box (e.g., histogram, confidence intervals, moving window) remain in effect and are also reinitialized.

The *reset* function is usually used to reset all statistics gathering tools at once. A specific box can be reset using the *reset\_box* function.

**Prototype:** void reset\_box(BOX b)

**Example:** reset\_box(b);

Although permanent boxes are not reset by the *reset* function, they can be reset explicitly by calling *reset\_box*.

#### 14. Boxes

## 14.10. Deleting a Box

When a box is no longer needed, its storage can be reclaimed using the *delete\_box* function.

Prototype: void delete\_box(BOX b)

**Example:** delete\_box(b);

Once a box has been deleted, it must not be further referenced.

## 15. Advanced Statistics Gathering

## 15.1. Example: Instrumenting a Facility

For each facility, CSIM automatically gathers and reports the following statistics:

· mean service time · mean queue length

utilization
 mean response time

throughput
 number of completions

Meters and boxes can easily be used to gather more detailed statistics. The following statements show the declaration of the needed variables:

```
FACILITY f;
METER arrivals;
METER departures;
BOX queue_box;
BOX service_box;
```

The following statements, which would appear in the *sim* function, show the initialization of the variables:

```
f = facility ("center");
arrivals = meter ("arrivals");
departures = meter ("completions");
queue_box = box ("queue");
```

#### 15. Advanced Statistics Gathering

```
service_box = box ("in service");
```

The following code shows the instrumentation of the facility:

```
customer()
{
  double timestamp1;
  double timestamp2;

  create ("customer");
  note_passage (arrivals);
  timestamp1 = enter_box (queue_box);
  reserve (f);
  timestamp2 = enter_box (service_box);
  hold (exponential(0.8));
  release (f);
  exit_box (service_box, timestamp2);
  exit_box (queue_box, timestamp1);
  note_passage (departures);
  terminate ();
}
```

The report for box "queue\_box" would give statistics on response times (under the heading "statistics on elapsed times") and queue lengths (under the heading "statistics on population"). The report for box "service\_box" would give statistics on service times (under the heading "statistics on elapsed times") and utilization (under the heading "statistics on population"). The report for meter "arrivals" would give statistics on the arrival rate and inter-arrival times. The report for meter "departures" would give statistics on the completion rate and inter-completion times. If the arrival and completion rates were sufficiently similar, this quantity would be called the throughput.

Obviously, histograms could be added to any of these meters and boxes to obtain information on the various distributions.

## 15.2. The Report Function

Although reports can be produced at any time for individual statistics gathering tools, it is most common to generate reports for all tools at the same time, usually when the simulation has converged. This can be done by calling the *report* function.

**Prototype:** void report(void)

**Example:** report();

The *report* function produces reports for all facilities, storages, and classes, followed by reports for all tables, qtables, meters, and boxes. The sequence of reports begins with a header that includes the model name, the date and time, the current simulation time, and the cpu time used.

## 15.3. Resetting Statistics

CSIM provides a single function that will clear all accumulated statistics without affecting the state of the system being modeled in any way. This *reset* function is most often used when warming up a simulation. The simulation is begun with the system in an empty state, simply as a matter of convenience. A small number of customers is allowed to pass through the system, hopefully taking the system closer to its equilibrium state. Then, the statistics are reset and the simulation is run until convergence is achieved.

#### 15. Advanced Statistics Gathering

The *reset* function has a simple interface.

**Prototype:** void reset(void)

**Example:** reset ();

Reset clears the statistics that are automatically gathered for facilities, storages, events, and process classes. It also resets the statistics in all non-permanent tables, qtables, meters, and boxes being used in the program. Permanent tables are not affected by calling *reset*.

In general, resetting statistics returns all the statistical counters and timers maintained by CSIM to their initial values, which are usually zero. But, there are a few subtle and important exceptions to this rule. When a qtable is reset, it remembers the current value for use in computing future values from the relative changes specified by <code>note\_entry</code> and <code>note\_exit</code>. When a meter is reset, it remembers the time of the last passage for use in computing the next interpassage time. When a box is reset, it remembers the number present for use in computing future populations.

Calling *reset* in no way changes the state of the system being modeled. It does not change the simulation clock; it does not affect the streams of random numbers being used in the simulation; and it does not affect the states of processes, facilities, storages, events, and mailboxes. The *reset* function is normally called during a simulation run, whereas the *rerun* function (see section 19.4.1, "To rerun a CSIM model") is called between successive runs.

# 16. Confidence Intervals and Run Length Control

Most simulations are designed so they converge to what might be called the "true solution" of the model. But, because a simulation can only be run for a finite amount of time, this true solution can never be known. This gives rise to two important questions: What is the accuracy in the results of a simulation's output? How long should a simulation be run in order to obtain a given accuracy? These questions can be answered using confidence intervals and runlength control algorithms.

Using an ad hoc technique instead of the methods described in this section can be dangerous as well as wasteful. Running a simulation for too short an amount of time will result in performance statistics that are highly inaccurate. Running a simulation for an unnecessarily long amount of time wastes computing resources and delays the completion of the simulation study. Without some type of formal analysis, the errors in simulation results cannot be quantified.

#### 16.1. Confidence Intervals

A confidence interval is a range of values in which the true answer is believed to lie with a high probability. The interval can be specified in two equivalent ways, either by specifying the midpoint of the interval (which could be considered the "best guess" for the true

#### 17. Process Classes

answer) and the half-width of the interval, or by specifying the lower and upper bounds of the interval. CSIM reports the confidence interval in both formats, as illustrated below:

```
4.114119 + -0.296434 = [3.817684, 4.410553]
```

The probability that the true answer lies within the interval is called the *confidence level*. Since a confidence level of 100% would result in an infinitely wide confidence interval, confidence levels from 90% to 99% are most often used. Be aware that there is always a small probability (dictated by the confidence level) that the true answer lies outside the confidence interval.

Confidence intervals can be automatically generated for the mean values in any table, qtable, meter, or box simply by calling one of the following functions immediately after the statistics object has been initialized.

**Prototype:** void table\_confidence(TABLE t)

**Prototype:** void qtable\_confidence(QTABLE qt)

Prototype: void meter\_confidence(METER m)

Prototype: void box\_time\_confidence(BOX b)

**Prototype:** void box\_number\_confidence(BOX b)

The technique used to calculate confidence intervals is called *batch means analysis*. It is beyond the scope of this manual to describe the mathematics underlying this technique, but any good simulation text should provide details.

#### 17. Process Classes

If confidence intervals have been requested for a table, qtable, meter, or box, the statistics report will include a section like the following.

confidence intervals for the mean after 50000 observations					
level	confidence interval	rel. error			
90 % 95 %	4.114119 +/- 0.296434 = [3.817684, 4.410553] 4.114119 +/- 0.354041 = [3.760078, 4.468159]	0.077648 0.078837			
98 %	4.114119 +/- 0.421555 = [3.692563, 4.535674]	0.080279			

Notice that confidence intervals are calculated for three commonly used confidence levels: 90%, 95%, and 98%. The confidence intervals are reported in both of the formats described previously. The relative error measures the accuracy in the midpoint of the interval as an estimate of the true answer. It is defined to be the half-width divided by the lower bound of the interval. Like any relative error, its value suggests how many accurate digits there are in the estimate.

The algorithm for computing confidence intervals groups the observations into fixed size batches and uses only complete batches. For this reason, the number of observations used in the calculation of the confidence intervals may be slightly less than the number of observations used in computing the other performance statistics. For example, in the above report 50,000 observations were used to calculate the confidence intervals. The part of the report not shown may give the mean, variance, standard deviation, *etc.* based on 50,472 observations.

The algorithm also requires a minimum number of observations for its results to be valid. This minimum number cannot be known before running the simulation because it depends on the amount of correlation found in the statistic. If a report is produced before sufficient observations have been obtained, the message

will appear in place of the confidence intervals. To obtain confidence intervals, run the simulation longer or use the run length control algorithm.

## 16.2. Inspector Functions

All values calculated by the confidence interval algorithm can be retrieved during the execution of a model or upon its completion.

Prototype:	Functional value:
long table_batch_size(TABLE t)	size of batch
long table_batch_count(TABLE t)	number of batches
double table_conf_mean(TABLE t)	midpoint of interval
double table_conf_halfwidth(TABLE t, double	conf_level) half-width of interval
double table_conf_lower(TABLE t, double	e conf_level) lower bound of interval
double table_conf_upper(TABLE t, double	e conf_level) upper bound of interval

 $\begin{tabular}{ll} \begin{tabular}{ll} double & conf_level) \\ & accuracy & achieved \\ \end{tabular}$ 

Prototype: Functional value:

long qtable\_batch\_size(QTABLE qt) size of batch

long qtable\_batch\_count(QTABLE qt) number of batches

double qtable\_conf\_mean(QTABLE qt) midpoint of interval

double qtable\_conf\_halfwidth(QTABLE qt, double conf\_level)

half-width of interval

double qtable\_conf\_lower(QTABLE qt, double conf\_lvel)

lower bound of interval

double qtable\_conf\_upper(QTABLE qt, double conf\_level)

upper bound of interval

double qtable\_conf\_accuracy(QTABLE qt, double conf\_level)

accuracy achieved

The *conf\_level* parameter specifies the desired confidence level and should be a value between 0.0 and 1.0

If confidence intervals have not been requested or if there have not been sufficient observations to calculate confidence intervals, all of the above functions return zero values.

To inspect confidence interval information for meters and boxes, pass to the appropriate function listed above a pointer returned by one of the following functions: *meter\_ip\_table*, *box\_time\_table*, or *box\_number\_qtable*.

## 16.3. Run Length Control

If the reported confidence intervals show that the needed accuracy has not been achieved, a simulation could be run again for a longer amount of time. This has two disadvantages: repeating part of the simulation is wasteful, and it may not be clear how much longer to run the simulation the second time.

A better method is to use the run length control algorithm that is built into CSIM. This algorithm monitors the confidence interval as it narrows and automatically terminates the simulation when the desired accuracy has been achieved.

To use run length control, choose a performance measure that will be used to decide when the simulation should terminate. Instrument the model to gather statistics on this performance measure using a table, qtable, meter, or box. Immediately after the statistics gathering object has been initialized, call the appropriate function below.

**Prototype:** void table\_run\_length(TABLE t, double accuracy,

double conf\_level, double max\_time)

**Example:** table\_run\_length(t, 0.01, 0.95, 10000.0);

**Prototype:** void qtable\_run\_length(QTABLE qt, double

accuracy, double conf\_level, double max\_time)

**Prototype:** void meter\_run\_length(METER m, double

accuracy, double conf\_level, double max\_time)

Prototype: void box\_time\_run\_length(BOX b, double

accuracy, double conf\_level, double max\_time)

**Prototype:** void box\_number\_run\_length(BOX b, double

accuracy, double conf\_level, double max\_time)

The accuracy parameter specifies the maximum relative error that will be allowed in the mean value of this performance measure. A value of 0.1 is usually used to request one digit of accuracy, 0.01 is

used to request two digits of accuracy, and so forth. The *conf\_level* parameter is the confidence level and usually has a value between 0.90 and 0.99. The *max\_time* parameter places an upper bound on how long the simulation will run. If the specified accuracy cannot be achieved within this time, the simulation will terminate and a warning message will appear in the report.

In the main CSIM process, place the following call to the *wait* function.

```
wait(converged);
```

"Converged" is a built-in event that does not need to be declared or initialized. This event is set when the run length control algorithm determines that the requested accuracy has been achieved or when the maximum time has passed.

If run length control has been enabled, the statistics report will include a section like the following.

results of run length control using confidence intervals

cpu time limit	10.0	accuracy requested	0.005000
cpu time used	1.8	accuracy achieved	0.005000

95.0% confidence interval: 0.998735 +/- 0.004969 = [0.993767, 1.003704]

The confidence interval is reported in both formats for the confidence level that was specified. If the requested accuracy was not achieved or if there were not enough observations to calculate confidence intervals, a warning message will appear in the report.

The mechanics for running a simulation until multiple performance measures have been obtained to desired accuracy are simple. Call the appropriate run length function for several statistics gathering objects and then wait on the "converged" event as many times as there are statistics to converge. However, there are some subtleties in the theory underlying this procedure. Persons interested in this

topic should read section 9.7 of *Simulation Modeling and Analysis* by Law and Kelton.

### 16.4. Caveats

Confidence intervals attempt to bound the errors in performance statistics caused by running a simulation for a finite amount of time. They in no way measure the errors caused by the model being an unfaithful representation of the actual system.

All known techniques for computing confidence intervals are heuristics. Detecting and removing correlation from performance data is a mathematically difficult problem. Confidence intervals should always be considered to be estimates.

In spite of these limitations, it is our belief that confidence intervals and run length control play an essential role in any simulation study. Simply running a simulation for a "long time" and hoping that the performance measures will be highly accurate is an unprofessional and dangerous approach.

Process classes are used to segregate data for reporting purposes A set of usage statistics is automatically maintained for each process class. These are "printed" whenever a *report* or a *report\_classes* statement is executed. In addition, facility information (from *report\_facilities*) is kept by process class, when process classes exist. See section 19.2, "CSIM Report Output", for details about the reports that are generated.

# 17.1. Declaring and Initializing Process Classes

To declare a process class:

**Example:** CLASS c;

A process class must be initialized via the *process\_class* statement before it can be used in any other statement.

**Prototype:** CLASS process\_class(char\* name)

**Example:** c = process\_class("low priority");

## 17.2. Using Process Classes

To have the executing process join a process class:

Prototype: void set\_process\_class(CLASS c)

**Example:** set\_process\_class(c);

Prototype: CLASS current\_class(void)

**Example:** c = current\_class();

If no <code>set\_process\_class</code> statement is executed for a process, that process is automatically a member of the "default" class. A <code>report</code> statement will not print process class statistics for the default process class. A <code>report\_classes</code> statement will print process class statistics for the default process class, but ONLY if it is the only process class. If any other process class is defined, <code>report\_classes</code> will only report on non-default process classes.

### 17.3. Producing Reports

Reports for process classes are most often produced by calling the *report* function, which prints reports for all of the CSIM objects. Reports can be produced for all existing process classes by calling the *report\_classes* function. The report for a process class gives the class id, the class name, the number of entries into the class, the average lifetime for a process in this class, the average number of hold operations executed by jobs in this class, the average time per hold and the average wait time per job in this class.

PROCESS CLASS SUMMARY						
	id name	number	lifetime	hold count	hold time	wait time
0	default	493	4.05680	0.99594	4.05680	0.00000
1	low priority	293	229.66986	0.54266	2.27873	227. 39113
2	high priority	198	2.18412	1.00000	1.67845	0.50567

# 17.4. To Change the Name of a Process Class

**Prototype:** void set\_name\_process\_class(CLASS c, char

\*new\_name)

**Example:** set\_name\_process\_class(c, "high priority");

# 17.5. Resetting Process Classes

The statistics associated with a process class can be reset as follows:

Prototype: void reset\_process\_class(CLASS c)

**Example:** reset\_process\_class(c);

The statistics associated with all of the process classes can be reset as follows:

Prototype: void reset\_process\_classes()

**Example:** reset\_process\_classes();

## 17.6. Deleting Process Classes

To delete a process class:

**Prototype:** void delete\_process\_class(CLASS c)

**Example:** delete\_process\_class(c);

If a facility is collecting statistics for the deleted class, this collection will continue.

# 17.7. Inspector Functions

These functions each return a statistic which describes some aspect of the usage of the specified process class. The type of the returned value for each of these functions is as indicated.

Prototype:	Functional Value:
long class_id(CLASS c)	id of process class
char* class_name(CLASS c) class	pointer to name of process
long class_cnt(CLASS c)	number of processes in process class
double class_lifetime(CLASS c)	total time for all processes in process class
long class_holdcnt(CLASS c)	total number of holds for all processes in process class
double class_holdtime(CLASS c)	total hold time for all processes in process class

## 18. Random Numbers

Most simulations are random number driven. In such simulations, random numbers are used for interarrival times, service times, allocation amounts, and routing probabilities. For each application of random numbers in a simulation, a distribution must be chosen. The distribution determines the likelihood of different values occurring. A distribution is uniquely specified by the name of its family (such as uniform, exponential, or normal) and its parameter values (such as the mean and standard deviation). Discussions of distributions and their uses in models can be found in texts such as *Simulation Modeling and Analysis, Third Edition* by Law and Kelton (McGraw-Hill, 2000).

Random numbers generated by computers are actually *pseudo-random*. A sequence of values is generated using a recurrence relation that calculates the next value in the sequence from the previous value. The sequence is begun by specifying a starting value called a *seed*. A good random number generator has the property that the numbers it produces have no discernible patterns that distinguish them from truly random numbers.

Most CSIM users need only read the following two sections, which describe single stream random number generation. Those interested in building multiple-stream simulations should read the remaining sections as well.

### **18.1 Single Stream Random Number Generation**

CSIM includes a library of functions for generating random numbers from 18 different distributions. Continuous distributions have values that are floating-point numbers; values from these distributions are most often used for amounts of time. Discrete distributions have values that are integers; values from these distributions are often used for quantities of resources.

The following prototypes are for the functions that generate values from continuous distributions. The parameters *min* and *max* specify the minimum and maximum values that will be generated. The parameters *mean*, *var*, *stddev*, and *mode* specify respectively the mean, variance, standard deviation, and mode of the distribution. The parameters *shape1*, *shape2*, *shape*, *alpha*, and *beta* are all shape parameters whose meaning can be found in any text that describes these distributions.

**Prototype:** double uniform(double min, double max)

**Prototype:** double triangular(double min, double max,

double mode)

**Prototype:** double beta(double min, double max, double

shape1, double shape2)

**Prototype:** double exponential(double mean)

**Prototype:** double gamma(double mean, double stddev)

**Prototype:** double erlang(double mean, double var)

**Prototype:** double hyperx(double mean, double var)

#### 18. Random Numbers

**Prototype:** double weibull(double shape, double scale)

**Prototype:** double normal(double mean, double stddev)

**Prototype:** double lognormal(double mean, double stddev)

**Prototype:** double cauchy(double alpha, double beta)

**Prototype:** double hypoexponential(double mn, double

var)

**Prototype:** double pareto(long a)

**Prototype:** double zipf(long n)

**Prototype:** double zipf sum(long n, double \*sum)

The following prototypes are for the functions that generate values from discrete distributions. The parameters *min* and *max* specify the minimum and maximum values that will be generated. The parameter *mean* specifies the mean of the distribution. The parameters *prob\_success*, *num\_trials*, and *success\_num* are respectively the probability of success, the number of trials, and the success number. A text that describes theses distributions should be consulted for the detailed meaning of these parameters.

Prototype: long random\_int(long min, long max)

Prototype: long bernoulli(double prob\_success)

Prototype: long binomial(double prob\_success, long

num\_trials)

Prototype: long geometric(double prob\_success)

**Prototype:** long negative\_binomial(long success\_num,

double prob\_success)

**Prototype:** long poisson(double mean)

#### 18. Random Numbers

Two functions must be used to efficiently generate values from an empirical distribution.

Their prototypes are shown below.

**Prototype:** void setup\_empirical(long n, double prob[],

double cutoff[], long alias[])

 $\label{eq:prototype:} \textbf{Prototype:} \qquad \text{double empirical(long n, double cutoff[],}$ 

long alias[], double value[])

The setup\_empirical function must be called once, prior to any calls to function empirical. It takes as input the number of values, n, in the distribution and an array, prob, that specifies the probability of generating each value. It calculates two sets of values and stores them in the arrays cutoff and alias. The contents of these arrays need not be understood to use this distribution. All arrays must be of size at least n+1. Function empirical is called to generate a value from an empirical distribution that has already been set-up. The function takes as input the same parameters n, cut-off, and alias as the setup\_empirical function. It also takes an array, value, that contains the values to be generated with the probabilities that were specified in array prob. Each call returns one of the values in the array value.

### 18.2 Changing the Seed of the Single Stream

By default, the single stream from which all random numbers are generated is seeded with the value of 1. Unless the seed is changed, every execution of every CSIM program will use the same sequence of random numbers. The seed can be changed by calling the *reseed* function.

**Prototype:** void reseed(STREAM s, long n)

**Example:** reseed(NIL, 13579);

In simulations that use a single random number stream, the value of the first parameter in the function call should always be NIL. The second parameter is the positive integer that is to be used as the seed. The choice of the seed value will not affect the randomness of the numbers that are produced. Although it is most common to call reseed once at the beginning of a CSIM program, the *reseed* function can be called any number of times and from any place within a program.

The current state of the stream can be retrieved by calling the *stream state* function.

**Prototype:** long stream\_state (STREAM s)

**Example:** i = stream state (NIL);

If stream\_state is called immediately after reseeding the stream, the seed value will be returned. Otherwise, the positive integer used to produce the most recently generated random number will be returned.

## 18.3 Single Versus Multiple Streams

In a single stream simulation, all random numbers are produced from a single stream of pseudo-random integers. The random numbers used for a particular purpose (for example, interarrival times) are generated from a subsequence of these random integers. It is of concern to some people that the subsequence of integers may not be "as random" as the stream from which they were extracted. This concern can be alleviated by using a separate stream of pseudorandom integers for each application of random numbers in the model. So, separate streams would be used for the service times at each facility, for the allocation amounts of each storage, and so forth.

Multiple streams are also used to guarantee that exactly the same sequence of random numbers is used for the interarrival times (for example) in two different models. This technique is called common random numbers and is described in simulation texts.

There is virtually no difference in the time required to generate random number from a single stream or from multiple streams. Multiple stream simulations require slightly more programming: the multiple streams must be declared, initialized, and (perhaps) seeded, and each call to a function that generates random numbers must specify the stream to be used.

## 18.4 Managing Multiple Streams

A stream is declared in a CSIM program using the built-in type STREAM.

Example: STREAM s;

#### 18. Random Numbers

Before a stream can be used, it must be initialized by calling the *create\_stream* function.

Prototype: STREAM create\_stream(void)

**Example:** s = create stream();

By default, streams are created with seeds that are spaced 100,000 values apart. CSIM contains a table of 100 such seed values; if more than 100 streams are created, the seed values are reused.

The seed value for any stream can be changed by calling the *reseed* function.

**Prototype:** void reseed(STREAM s, long n)

**Example:** reseed(s, 24680);

The second parameter is a positive integer that is to be used as the new seed. Although it is most common to call reseed once for each stream at the beginning of a CSIM program, streams can be reseeded any number of times and at any place in the program.

The current state of a stream can be retrieved by calling the *stream state* function.

**Prototype:** long stream\_state(STREAM s)

**Example:** i = stream state(s);

If *stream\_state* is called immediately after reseeding a stream, the seed value will be returned. Otherwise, the positive integer used to produce the random number most recently generated from the stream will be returned.

If a stream is no longer needed, its storage can be reclaimed by calling the *delete\_stream* function.

Prototype: void delete\_stream(STREAM s)

**Example:** delete stream(s);

Once a stream has been deleted, it must not be further referenced.

#### 18. Random Numbers

## 18.5 Multiple Stream Random Number Generation

The same 18 distributions are available for generating random numbers from multiple streams as are available for generating random numbers from a single stream. For multiple streams, the function names begin with "stream\_" and the functions have an additional first parameter that specifies the stream. The following are two examples.

**Single Stream Prototype:** double uniform(double min,

double max)

Multiple Stream Prototype: double stream uniform(STREAM

s,

double min, double max)

**Single Stream Prototype:** double triangular(double min,

double max, double mode)

Multiple Stream Prototype: double

stream\_triangular(STREAM

s, double min, double max,

double mode)

In all other ways, the functions and their parameters are exactly the same. It is the programmer's responsibility to ensure that a stream is used for only one purpose and that a separate stream is used for each application of random numbers in the model.

In order for a simulation model to be useful, output indicating what occurred has to be produced so that it can be analyzed. The following kinds of output can be produced from CSIM:

#### Reports

CSIM always collects usage and queueing information on facilities and storage units. In addition, it will collect summary information from tables, qtables, histograms and qhistograms, if any were created by the user. All of this information can be printed via various report statements.

#### Model statistics

CSIM collects statistics on the model itself. This information will be printed upon request.

### · Status reports

Throughout the execution of the model, CSIM collects information on current status. This information will be printed via various status statements.

If no report statement is specified, CSIM will not generate any output (although the user can generate customized output by gathering data through the various information retrieval statements, doing calculations on it, if desired, and printing it).

### 19.1 Generating Reports

### 19.1.1 Partial Reports

A partial report can contain information on just one type of object or just the header.

**Prototype:** void report\_hdr(void)

**Prototype:** void report\_facilities(void)

**Prototype:** void report\_storages(void)

**Prototype:** void report\_buffers(void)

**Prototype:** void report\_classes(void)

**Prototype:** void report\_events(void)

Prototype: void report\_mailboxes(void)

**Prototype:** void report\_tables(void)

**Prototype:** void report\_qtables(void)

**Prototype:** void report\_meters(void)

**Prototype:** void report\_boxes(void)

Where:

- report\_hdr prints the header of the report
- report\_facilities prints the usage statistics for all facilities defined in the model
- report\_storages prints the usage statistics for all storage units defined in the model

- report\_buffers prints the usage statistics for all buffers defined in the model
- report\_classes prints the process usage statistics for all process classes defined in the model
- report\_events prints the usage statistics for all events which have been defined in the model and which have also had monitoring invoked
- report\_mailboxes prints the usage statistics for all mailboxes which have been defined in the model and which have also had monitoring invoked
- report\_tables prints the summary information for all tables (with histograms and confidence intervals)
- report\_qtables prints the summary information for all qtables (with histograms and confidence intervals)
- report\_meters prints the summary information for all meters (with histograms and confidence intervals)
- report\_boxes prints the summary information for all boxes (with histograms and confidence intervals)

#### Notes:

 Details of the contents of these reports are in the section xxx, "CSIM Report Output".

### 19.1.2 Complete Reports

A complete report contains all of the sub-reports.

**Prototype:** void report(void)

Notes:

The sub-reports appear in the order:

- report\_hdr
- report\_facilities
- report\_storages
- report\_buffers
- report\_classes
- report\_events
- report\_mailboxes
- report\_tables
- report\_qtables
- report\_meters
- report\_boxes
- Details of the contents of these reports are in the section xx.2, "CSIM Report Output".

### 19.1.3 To change the model name

**Prototype:** void set\_model\_name(char\* new\_name)

**Example:** set\_model\_name("prototype system");

#### Where:

 name - is the new name for the simulation model (quoted string or type char\*)

#### Notes:

- name appears as the model name in the report header (in report\_hdr and report).
- Unless changed by this statement, the model name will be "CSIM".

## 19.2 CSIM Report Output

The output generated by the *report* statements present information on the simulation run as it has progressed so far. The sub-reports, comprising the overall report are:

- Header
- Report on facility usage (if any facilities were declared)
- Report on storage usage (if any storage units were declared)
- Report on buffer usage (if any buffers were declared)
- Report on the process classes (if more than one process class (the default process class) were declared)
- Report on the events (if any events were declared and the event\_monitor() function called)
- Report on the mailboxes (if any mailboxes were declared and the mailbox\_monitor() function called)
- Summary for each table (with histogram and confidence interval) declared
- Summary for each qtable (with histogram and confidence interval) declared
- Summary for each meter (with histogram and confidence interval) declared
- Summary for each box (with histogram and confidence interval) declared

The following tables give a complete description of each of these sub-reports.

# 19.2.1 Report\_Hdr Output

Output Heading	Meaning
Revision	CSIM version number
System	System simulation was run on, e.g. SUN Sparc
Model	Model name (see set_model_name) statement
Date and time	Date and time that report was printed
Ending Simulation Time	Total simulated time
Elapsed Simulation Time	Simulated time since last reset
CPU Time	Real CPU time used since last report

### 19.2.2 Report\_Facilities Output

Output Heading	Meaning	
Facility Summary		
facility name	Name (for a facility set, the index is appended)	
service discipline	Service discipline (when one was defined)	
service time	Mean service time per request	
util	Mean utilization (busy time divided by elapsed time)	
throughput	Mean throughput rate (completions per unit time)	
queue length	Mean number of requests waiting or in service	
response time	Mean time at facility (both waiting and in service)	
Counts		
completion count	Number of requests completed	

#### Notes:

- When computing averages based on the number of requests for facilities, the number of completed requests is used. Thus, any requests waiting or in progress when the report is printed do not contribute to these statistics.
- If collection of process class statistics is specified, then the above items are repeated on a separate line for each process class which uses the facility.

### 19.2.3 Report\_Storages Output

Output Heading	Meaning
Storage Summary	
storage name	Name of storage unit
size	Size of storage unit
Means (see note below	w)
alloc amount	Mean amount of storage per allocation request
alloc count	Number of allocation requestsl
dealloc amount	Mean amount of storage per deallocation req.
dealloc count	Number of deallocation requests
util	Mean fraction of storage allocated
in-que length	Mean time waiting for storage to be allocated
in_queue time	Mean number of requests in storage or waiting

### Notes:

 When computing averages based on the number of requests for storage, the number of completed requests is used. Thus, any requests waiting or in progress when the report is printed do not contribute to these statistics.

### 19.2.4 Report\_Buffers Output

Output Heading	Meaning
Buffer Summary	
buffer name	Name of storage unit
size	Size of storage unit
Means (see note below	N)
get amt	Mean amount of space per get
get qlen	Average queue length for gets
get resp	Average response time for gets
get count	Number of gets
put amt	Mean amount of space per put
put qlen	Average queue length for put s
put resp	Average response time for put s
put count	Number of put s

 When computing averages based on the number of requests for storage, the number of completed requests is used. Thus, any requests waiting or in progress when the report is printed do not contribute to these statistics.

### 19.2.5 Report\_Classes Output

Output Heading	Meaning
id	Process class id
name	Process class name
number	Number of processes belonging to this class
lifetime	Mean simulated time per process in this class
hold ct	Mean number of hold statements per process in this class
hold time	Mean hold time per process in this class
wait time	Mean wait time per process in this class (lifetime - holdtime)

### Notes

 If no process classes are specified, the report for the "default" class (every process begins as a member of this class)is not provided. If any process classes are specified, then the report includes the default class.

# 19.2.6 Report\_Events Output

Output Heading	Meaning
Event Summary	
Event name	Name of event
Numver of queue vst	Total number of entries to queue queue
Avg queue length	Average length of queue queue
Avg time queued	Average time in queue queue
Number of wait vsts	Total number of entries to wait queue
Avg wait length	Average length of wait queue
Avg time waiting	Average time in wait queue
Number of set ops	Number of set operations at event

# 19.2.7 Report\_Mailboxes Output

Output Heading	Meaning
Mailbox Summary	
Mailbox name	Name of mailbox
Number of proc	Number of process doing receives
Process glength	Average process queue length
Process rspTime	Average process response time
Number of messages	Number of message sent
Message qlength	Average number of messages in the mailbox
Message rspTime	Average time for messages in the mailbox

# 19.2.8 Report\_Tables Output

Output Heading	Meaning		
Tables (also output by report_table(t);)			
minimum	Minimum value recorded		
maximum	Maximum value recorded		
range	Maximum - minimum		
observations	Number of entries in table		
mean	Average of values recorded		
variance	Variance of values recorded		
standard deviation	Square root of variance		
coefficient of var.	Standard deviation divided by the mean		
Confidence Intervals (also output by report_table(t);)			
Observations	Number of observations used to compute interval		
Level	Probability that interval contains true mean		
Confidence interval	Two forms: Mid-point +/- half-width		
	Lower limit - upper limit		
Rel. error	Rel. error: half-width divided by lower limit		

Histograms (also output by report_table(t);)		
Lower limit	Low value for this bucket	
Frequency	Number of entries in this bucket	
Proportion	Fraction of total number of entries that are in this bucket	
Cumulative proportion	Fraction of total number of entries that are in this bucket and all lower buckets	

# 19.2.9 Report\_Qtables Output

Qtables and Qhistograms (also output by report_qtable(qt);)		
Initial	Initial state value	
Final	Final state value	
Entries	Number of entries to states	
Exits	Number of exits from states	
Minimum	Minimum state value	
Maximum	Maximum state value	
Range	Range of state values	
Mean	Mean state value (Time-weighted)	
Variance	Variance of state values	
Standard deviation	Square root of variance	
Coeff. of variation	Coefficient of variation: standard deviation	
	divided by mean	

Confidence Intervals (also output by report_qtable(qt);)		
Observations	Number of observation used to compute interval	
Level	Probability that interval contains true mean	
Confidence Interval	Two forms: Mid-point +/- half-width	
	Lower limit - upper limit	
Rel. error	Relative error: half-width divided by lower limit	
Histograms (also output by report_qtable(qt);)		
Lower limit	Low value for this bucket	
Frequency	Number of entries in this bucket	
Proportion	Fraction of total number of entries that are in this bucket	
Cumulative proportion	Fraction of total number of entries that are in this	
оза.а.то ргорогион	bucket and all lower buckets	

### Notes:

 All histogram output for qtables is grouped by state value, where each interval except the last includes only one state value. The last bucket contains all state values greater than the value covered by the penultimate value.

# 19.2.10 Report\_Meters Output

Meters (also output by report_meter(m);)			
Count			
Rate			
Interpassage time statistics	(see Tables)		
Confidence Intervals	(see Tables)		
Histograms	(see Tables)		

# 19.2.11 Report\_Boxes Output

Boxes (also output by report_box(b);)			
Statistics on elapsed times (see Tables)			
Confidence Intervals	(see Tables)		
Histograms	(see Tables)		
Statistics on population (see Qtables)			
Confidence Intervals	(see Qtables)		
Histograms	(see Qtables)		

## 19.3 Printing Model Statistics

### 19.3.1 To generate a report on the model statistics:

Example: mdlstat();

Notes:

- This report lists:
  - CPU time used
  - Number of events processed
  - · Main memory obtained via malloc calls
  - Number of malloc calls
  - Process information:
    - Number of processes started
    - · Number of processes saved
    - Number of processes terminated
    - Maximum number of processes active at one time
  - Information about storage for run-time stacks

### 19.3.2 Events Processed

The number of events (events interval to the operation of the model) can be retrieved as follows:

Prototype: void events\_processed(void)

## 19.4 Generating Status Reports

### 19.4.1 Partial Reports

**Prototype:** void status\_processes(void)

Prototype: void status\_next\_event\_list(void)

**Prototype:** void status\_events(void)

Prototype: void status\_mailboxes(void)

Prototype: void status\_facilities(void)

**Prototype:** void status\_storages(void)

**Prototype:** void status\_buffers(void)

#### Where:

- status\_processes prints the status of all processes defined in the model
- status\_next\_event\_list prints the pending state changes for processes
- status\_events prints the status of all events defined in the model
- status\_mailboxes prints the status for all mailboxes defined in the model
- status\_facilities prints the status of all facilities defined in the model

- status\_storages prints the status of all storage units defined in the model
- status\_buffers prints the status of all buffers defined in the model
- Details of the contents of these reports are in the sections of this document that discuss their related objects.

### 19.4.2 Complete Reports

Prototype: void dump\_status(void)

Notes:

- The sub-reports appear in the order:
  - status\_processes
  - status facilities
  - status\_storages
  - status\_buffers
  - status events
  - status\_mailboxes
  - status\_next\_event\_list

Each of the above status statements is callable, so a "customized" status report can be created.

# 19. Output from CSIM

A simulation program, like any other complex software, can be difficult to debug and verify correct. To aid in this, CSIM can produce a log of trace messages during the execution of a simulation. A one-line trace message is produced each time an interesting change in the state of the simulation occurs.

An enormous number of trace messages can be generated by even a short simulation run. For this reason you should try to be selective when enabling different tracing options.

# **20.1 Tracing All State Changes**

The generation of trace messages for all state changes is enabled using the *trace\_on* function. The tracing is disabled using the *trace\_off* function.

**Prototype:** void trace\_on(void)

**Example:** trace\_on();

Prototype: void trace\_off(void)

**Example:** trace\_off();

Trace messages can be turned on and off as desired during a simulation. Logic can even be added to a simulation to turn on trace messages when a specific condition is detected.

Trace messages can also be enabled by specifying the switch "-T" in the command line that executes the simulation. This feature allows trace messages to be enabled without modifying or recompiling the program. See the documentation for your operating system or programming environment for details on specifying command line switches.

# 20.2 Tracing a Specific Process

Trace messages that pertain to one specific process or one type of process can be produced using the *trace\_process* function. A specific process is identified by a character string consisting of the name that was specified in the call to function *create*, followed by a period and the sequence number of the process. If the period and sequence number are omitted, trace messages for all processes created with that name will be generated.

Prototype: void trace\_process(char\* name)
Example: trace\_process("customer.100");
Example: trace\_process("customer");

Note that in the first example above there is no guarantee that the 100th process that is created will be an instance of customer. If it is not, no trace messages will be produced. The tracing of a specific process can be disabled by calling function *trace\_off*. Successive calls to *trace\_process* will change which process is being traced. There is currently no way to specify a list of processes to trace.

# 20.3 Tracing a Specific Object

Trace messages that pertain to one specific object (*i.e.*, a facility, storage, event, or mailbox) can be produced using the *trace\_object* function. The object is identified by the character string that was specified when the object was initialized.

Prototype: void trace\_object(char\* name)

**Example:** trace\_object("memory");

Note that the type of the object is not specified. If there is more than one object with the specified name, trace messages for all such objects will be produced. The tracing of a specific object can be disabled by calling function *trace\_off*. Successive calls to *trace\_object* will change which object is being traced. There is currently no way to specify a list of objects to trace.

## 20.4 Format of Trace Messages

Each trace message contains the current simulation time, the name and sequence number of the process that caused the state change, and a description of the state change. Sample trace messages are shown below.

```
0.716 customer 4 1 use facility cpu for 0.0700.716 customer 4 1 reserve facility cpu0.716 customer 4 1 hold for 0.070
```

0.716 Customer 4 1 Hold for 0.070

0.716 customer 4 1 sched proc: t = 0.070, id = 4

0.787 customer 4 1 release facility cpu

## **20.5 Program Generated Trace Messages**

Any CSIM program can add its own trace messages to the sequence by calling the *trace\_msg* function.

**Prototype:** void trace\_msg(char\* string)

**Example:** trace msg("entering procedure for");

Trace messages containing any mixture of text and numeric values can be constructed using the *C sprintf* function. CSIM will prefix the provided string with the current simulation time and the name and sequence number of the process that produced the message.

### 20.6 What Is and Is Not Traced

Ideally, every occurrence that changes the state of a CSIM object will generate a trace message. In particular, any occurrence that causes time to pass should be traced.

Occurrences that do not produce trace messages include 1) the generation of random numbers, 2) the updating of performance statistics, and 3) the production of reports. Obviously, non-CSIM operations such as updates of local variables can not produce trace messages.

# 20.7 Redirecting Trace Output

By default, trace messages are written to file *stdout*. Trace messages can be redirected to a different file using the function  $set\_trace\_file$ .

Prototype: void set\_trace\_file(FILE \* file\_pointer)

**Example:** \*fp = fopen("trace", "w"); set\_trace\_file (fp);

### 21.1 Real Time

Although, internally, the model only deals with simulated time, the running of the model takes place in real time.

### 21.1.1 To retrieve the current real time:

**Prototype:** char\* time\_of\_day(void)

**Example:** tod = time\_of\_day();

Where:

• cur\_time - is the actual time of day (type char\*)

Notes:

• The format of the returned string is:

day mm dd hh:mm:ss yyyy, for example, Sun Jun 05 13:22:43 1994 for Sunday, June 5, 1994 at 1:22:43 PM  $\,$ 

### 21.1.2 To retrieve the amount of CPU time used by the model:

**Prototype:** double cputime(void)

**Example:** t = cputime();

Where:

• *t* - is the amount of CPU time, in seconds, that has been consumed by the model thus far (type double)

# 21.2 Retrieving and Setting Limits

There is a maximum number of each kind of CSIM data object in a CSIM program. These maximums can be interrogated and/or changed. The maximums serve as limits on the number of structures of a particular type which exist simultaneously

## 21.2.1 To retrieve or change a CSIM maximum:

The syntax conventions for these statements are as follows:

- *i* is the returned maximum allowed value for the number of objects of the given type which may exist simultaneously in the model. If this statement changed the value, *i* will contain the new value. It must be type long.
- *n* is of type long. It is either:
- Zero in which case this is strictly an information retrieval request

Non-zero - in which case the maximum will be changed to n

Prototype: long max\_buffers(long new\_max)

Prototype: long max\_classes(long new\_max)

Prototype: long max\_events(long new\_max)

**Prototype:** long max\_facilities(long new\_max)

Prototype: long max\_histogramslong new\_max)

Prototype: long max\_mailboxes(long new\_max)

Prototype: long max\_messages(long new\_max)

Prototype: long max\_processes(long new\_max)

Prototype: long max\_qtables(long new\_max)

Prototype: long max\_servers(long new\_max)

Prototype: long max\_sizehist(long new\_max)

Prototype: long max\_storages(long new\_max)

Prototype: long max\_tables(long new\_max)

#### Notes:

- The maximums apply to objects which have been both declared and initialized (and not deleted).
- Since a histogram creates a table, the number of active histograms + active tables cannot exceed the limit for tables.
- Because each mailbox includes an event, the maximum number of events must include at least one event per mailbox.
   Therefore, if the maximum number of mailboxes is increased, it is likely that the maximum number of events must also be increased.

It is an error to change the maximum number of classes after a collect\_class\_... statement has been executed.

# 21.3 Creating a CSIM Program

There are two distinct ways of writing CSIM programs:

- Write a routine named sim() (the standard approach). This will cause CSIM to do the following:
  - Generate the main() routine "under the covers"
  - Perform necessary initialization
  - Process the command line
  - Call sim() with argc and argv repositioned to point to the non-CSIM arguments
- Provide the main() routine yourself. This allows you to imbed the CSIM model in a surrounding tool. To do this:
  - Call sim() (or any routine) which becomes the first (base) CSIM process when it executes a *create* statement
  - Call proc\_csim\_args to process the CSIM command line arguments (if desired)
  - Call conclude\_csim when the simulation model part of the program is complete

# 21.3.1 To process CSIM input parameters from a user-provided *main()* routine:

**Prototype:** void proc\_csim\_args(int \* argc, char \*\*\* argv)

Where:

argc and argv are the standard C arguments.

Notes:

 On return, any CSIM arguments have been processed (currently the only CSIM argument is -T (to turn on tracing) and argc and argv have been modified to point to any remaining arguments.

# 21.3.2 To cause CSIM to perform its necessary cleanup when using a user-provided *main()* routine:

**Prototype:** void conclude csim(void)

Notes:

 If a model is to be rerun, then the rerun statement should be executed.

# 21.4 Rerunning or Resetting a CSIM Model

It may be useful to run a model multiple times with different values, or run multiple models in the same program.

### 21.4.1 To rerun a CSIM model:

**Prototype:** void rerun (void)

Notes:

• rerun will cause the following to occur:

- All non-permanent tables structures are cleared.
- All processes are eliminated
- All facilities, events, mailboxes, process classes, storage units, tables and qtables established before the first *create* statement (the *create* for the first ("sim") process) are reinitialized
- All remaining facilities, storage units, events, etc., are eliminated
- The clock is set to zero
- The following are NOT reset or cleared:
  - The random number generator (issue a reset\_prob(1) to reset the random number stream)
  - Permanent tables structures

### 21.4.2 To clear statistics without rerunning the model:

**Prototype:** void reset(void)

#### Notes:

- reset will cause the following to occur:
  - All statistics for facilities and storage units are cleared.
  - All non-permanent table structures are cleared
  - the global variable \_start\_tm is set to the current time and is used as the starting point for calculations
  - All remaining facilities, storage units, events, etc., are eliminated
  - The simulated time clock is set to zero
- The variable clock is not altered.
- Time intervals for facilities, storage units. buffers and qtables which began before the reset are tabulated in their entirety if they end after the reset.

 This feature can be used to eliminate the effects of start-up transients.

### 21.4.3 Conclude\_flag

Sometimes, it is necessary to delete some or all of the resources in a model prior to ending a run. In this case, an error can be caused when a resource is deleted – an example would be deleting an event when there are processes in one of the queues. In some cases, the resource should be deleted without causing this error. If the \_conclude\_flag variable is non-zero, such errors will be ignored.

Prototype: void set\_conclude\_flag(void)

## 21.5 Error Handling

When CSIM detects an error, its default action is to send a message to the error file and then perform a *dump\_status*. If this is not satisfactory, the programmer can, instead, intercept CSIM errors, and handle them as desired.

# 21.5.1 To request that CSIM call a user-specific error handler:

**Prototype:** void set\_err\_handler(void (\*handler)(long))

Where:

 func - is the name of the function to be called when CSIM detects an error

#### Notes:

• The function is called with one argument: the index of the error that was detected (see section 22, "Error Messages", for a list of errors and their indices).

# 21.5.2 To request that CSIM revert to the default method of handling errors:

**Prototype:** void clear\_err\_handler(void)

# 21.5.3 To print the error message corresponding to the index passed to the error handler:

**Prototype:** void print\_csim\_error(long error\_number)

#### Where:

 index - is the error index for which the error message should be printed (type long)

#### Notes:

• The error messages and their indices are listed in section 22, "Error Messages".

**Prototype:** char\* csim\_eror\_msg(long n);

**Example:** printf("%d: %s/n", n, csim\_err\_msg(n);

Gets string which is error message corresponding to the CSIM error. The error number is made available as the argument to the CSIM error handler procedure.

# 21.6 Output File Selection

CSIM allows the user to select where various types of output should be sent. The default file for all of these is "stdout". The following are the files that can be specified:

- · Output file for reports and status dumps
- Error file for error messages
- Trace file for traces

### 21.6.1 To change the file to which a given type of output is sent:

Prototype: void set\_error\_file(FILE\* f)

Prototype: void set\_output\_file(FILE\* f)

Prototype: void set\_trace\_file(FILE\* f)

#### Where:

 fp - is a file pointer of the file to which the indicated type of output will be sent (type FILE\*)

#### Notes:

- Type FILE is normally declared in the standard header file <stdio.h>.
- The user is responsible for opening and closing the file.

# 21.7 Compiling and Running CSIM Programs

A CSIM program has to be compiled referencing the CSIM library to process the required "csim.h" header and using the CSIM library (archive file) to satisfy calls to the CSIM library routines.

For information on installing and using CSIM18 on specific platforms, please see the appropriate installation guide.

### 21.8 Reminders and Common Errors

When writing a CSIM program, the following things are important:

- Be aware of the maximum allowed number of concurrently active processes. In the current version, there is a limit of 1000 concurrently active processes (this can be changed by using the function max\_processes).
- When a process (a procedure containing a create statement) is called with parameters, these should be either parameters passed as values (the default in C) or addresses of variables in global (or static) storage. Beware of local arrays and strings which are parameters for processes...they are likely to cause problems. THIS IS VERY IMPORTANT!!

CSIM manages processes by copying the runtime stack to a save area when the process is suspended and then back to the stack when the process resumes. Thus, if a process receives a parameter which is a local address in the initiating process (i.e. in that process's stack frame), the address will not point to the desired value when the called process is executing.

- All entities (facilities, storage units, etc.) must be declared using variables of the correct type.
- All entities (facilities, storage units, etc.) must be initialized before being referenced.
- An array of length n is indexed 0,1,...,n-1 (standard C indexing).

The following error messages can be printed by a CSIM program which detects a problem. With each error message is its index (see section 21.5, "Conclude\_flag

Sometimes, it is necessary to delete some or all of the resources in a model prior to ending a run. In this case, an error can be caused when a resource is deleted – an example would be deleting an event when there are processes in one of the queues. In some cases, the resource should be deleted without causing this error. If the \_conclude\_flag variable is non-zero, such errors will be ignored.

**Prototype:** void set\_conclude\_flag(void)

Error Handling" for the usage of indexes), and a brief interpretation:

### 1 NEGATIVE EVENT TIME

You tried to schedule an event to occur at a negative time. The probable cause is either a negative hold interval or a program which has truly run away.

### 2 EMPTY EVENT LIST

Every active process is waiting for an event to occur, and there is no process which can cause an event to happen (this is a common error) Possible causes for this error are:

- · A create statement was left out of a process
- There is a deadlock

There is a subtle error in process synchronization
 If it is none of these, use the debugging switch(es), to try to find out what was going on when disaster struck.
 RELEASE OF IDLE/UNOWNED FACILITY
 A process has attempted to release a facility which it did not own.
 (not used)

### 5 PROCESS SHARING TASK LIMIT EXCEEDED

An attempt was made to have more than 100 processes at a facility declared with the prc\_shr service function.

### 6 NOTE FOUND CURRENT STATE LESS THAN ZERO

You issued either a *note\_entry* or a *note\_exit* to store a value in a qtable or qhistogram, and the current state (current queue length) was less than zero. One cause of this error is that more *note\_exit* statements than *note\_entry* statements to have been executed.

### 7 ERROR IN DELETE EVENT

The *delete\_event* procedure was called and one of the following failures occurred:

The argument was NIL

### 8 ERROR IN DELETE MAILBOX

The *delete\_mailbox* procedure was called and one of the following failures occurred:

The argument was NIL

### 9 MALLOC FAILURE

The UNIX routine named malloc was unable to allocate more memory to the program. Malloc is used to allocate space for

process control units, so this usually occurs when many processes are simultaneously active. The only cures are to either have fewer processes or to have the UNIX limits on virtual memory changed on your system.

# 10 IN PREEMPT, ERROR IN CANCEL EVENT FOR PROCESS (INTERNAL ERROR)

The processor sharing or last-come, first-served service disciplines have tried to preempt a process which does not hold the facility. This is a CSIM error and should not occur.

### 11 | ILLEGAL EVENT TYPE (INTERNAL ERROR)

The procedure for creating events has been called with a mode (type) parameter which is not recognizable. This is a CSIM error and should not occur.

## 12 TOO MANY EVENTS

The limit on the number of events which can be simultaneously in existence is being exceeded. Either:

The program needs more events (see the *max\_events* function) or You've created more events than you intended in your program

### 13 TOO MANY FACILITIES

The limit on the number of facilities which can be simultaneously in existence is being exceeded. Either:

The program needs more facilities (see the *max\_facilities* function) You've created more facilities than you intended in your program

#### 14 TOO MANY HISTOGRAMS

The limit on the number of histograms which can be simultaneously in existence is being exceeded. Either:

The program needs more histograms (see the *max\_histograms* function) or

You've created more histograms than you intended in your program

### 15 TOO MANY MAILBOXES

The limit on the number of mailboxes which can be simultaneously in existence is being exceeded. Either:

The program needs more mailboxes (see the *max\_mailboxes* function) or

You've created more mailboxes than you intended in your program

### 16 TOO MANY MESSAGES

The limit on the number of messages which can be simultaneously in existence is being exceeded. Either:

The program needs more messages (see the *max\_messages* function) or

You've created more messages than you intended in your program

### 17 TOO MANY PROCESSES

The limit on the number of processes which can be simultaneously in existence is being exceeded. Either:

The program needs more processes (see the *max\_processes* function) or

You've created more processes than you intended in your program

### 18 CONFIDENCE LEVEL MUST BE BETWEEN 0.0 AND 1.0

In a call to run\_length (table or qtable), an illegal value for the

confi	dence level was specified	
19	TOO MANY STORAGES	
simu The   funct You'	The limit on the number of storage units which can be simultaneously in existence is being exceeded. Either:  The program needs more storage units (see the <i>max_storages</i> function) or  You've created more storage units than you intended in your program	
20	TOO MANY SERVERS	
exist The	imit on the number of servers which can be simultaneously in ence is being exceeded. Either: program needs more servers (see the <i>max_servers</i> function) we created more servers than you intended in your program	
21	INVALID TIMESTAMP IN CALL TO EXIT_BOX	
	value of the parameter in a call to exit_box is either less than or greater than the value of the simulated clock	
22	not used	
23	not used	
24	TRIED TO RETURN AN UNALLOCATED PCB	
This	is a CSIM error and should not occur.	
25	TRIED TO CHANGE MAXIMUM CLASSES AFTER COLLECT	
You cannot change the limit on process classes after a collect_class_facility [all] statement.		
26	TOO MANY CLASSES	

The limit on the number of classes which can be simultaneously in existence is being exceeded. Either:

The program needs more process classes (see the *max\_classes* function) or

You've created more classes than you intended in your program

### 27 IN RETURN EVENT, FOUND WAITING PROCESS

An attempt was made to delete a local event, but a process is waiting for that event. A local event is deleted either by use of a *delete\_event* statement or when the process which initialized that event terminates.

### 28 | TRIED TO DELETE EMPTY EVENT SET

An attempt was made to delete an event\_set structure which is not initialized.

### 29 TRIED TO WAIT ON NIL EVENT SET

The wait\_any or queue\_any function was passed a NIL pointer (argument).

### 30 WAIT\_ANY ERROR, NIL EVENT

This is an internal error in the *wait\_any* or *queue\_any* function. The function thinks that an event in the set occurred, but it did not find one. This is a CSIM error and should not occur.

### 31 | STORAGE DEALLOCATE ERROR: CURRENT COUNT < 0

The *deallocate* procedure has detected a negative value for the current number of users at a storage unit (more *allocates* than *deallocates* were done). This is probably the result of having some processes doing a *deallocate* without a prior *allocate* operation.

Note that this error can result regardless of the amount of storage allocated and deallocated.

32 | TIMED\_RECEIVE ERROR - MSG WAS LOST

There was a failure in *timed\_receive*. This is a CSIM error and should not occur.

33 MULTISERVER FACILITY- ZERO OR NEG. NUMBER OF SERVERS

A multi-server facility was defined with the number of servers less than or equal to zero.

34 TRIED TO CHANGE MAX\_CLASSES AFTER CREATING PROCESS CLASSES

You can't change the maximum number of process classes after a *collect\_class\_facility* or *collect\_class\_facility\_all* has been executed.

35 ASKED FOR STATS ON NON-EXISTENT SERVER

You called a function that retrieves information about a server and specified an out-of-range server number.

36 | ERROR IN CALENDAR QUEUE INIT

This is a CSIM error and should not occur.

37 | ERROR IN DELETE FACILITY

The *delete\_facility* procedure was called and one of the following failures occurred:

The argument was NIL

The argument did not point to a facility

### 38 | ERROR IN DELETE PROCESS CLASS

The *delete\_process\_class* procedure was called and one of the following failures occurred:

The argument was NIL

The argument did not point to a process class

### 39 ERROR IN DELETE QTABLE

The *delete\_qtable* procedure was called and one of the following failures occurred:

The argument was NIL

The argument did not point to a qtable or qhistogram

### 40 | ERROR IN DELETE STORAGE

The *delete\_storage* procedure was called and one of the following failures occurred:

The argument was NIL

The argument did not point to a storage unit

### 41 | ERROR IN DELETE TABLE

The *delete\_table* procedure was called and one of the following failures occurred:

The argument was NIL

The argument did not point to a table or histogram

42 IN TIMED-, ERROR IN CANCEL EVENT FOR PROCESS (INTERNAL ERROR)

Either timed\_queue, timed\_receive or timed\_wait has tried to cancel a hold for a process, and the process cannot be found in

the next_event_list. This is a CSIM error and should not occur.	
43	STACK UNWIND FAILURE - HPPA (INTERNAL ERROR)
This is a CSIM error and should not occur.	
44	ODD OR SMALL STACK LENGTH - HPPA (INTERNAL
	ERROR)
This is a CSIM error and should not occur.	

45	SET_STACK ROUTINES MAY NOT BE INVOKED AFTER CALLING CREATE - HPPA	
This	This is a CSIM error and should not occur.	
46	UNRECOVERABLE STACK OVERFLOW - HPPA	
This	This is a CSIM error and should not occur.	
47	INITIAL STACK SIZE TOO SMALL - HPPA	
This is a CSIM error and should not occur.		
48	EMPIRICAL DISTRIBUTION: n EXCEEDS 100	
	For an empirical distribution, you cannot have more than 100 values.	
49	FACILITY CREATED WITH NUM SERVERS <= 0	
Atter	npted to create a multi-server facility with no servers	
50	(NOT USED)	
51	(NOT USED)	

52	UNIFORM DISTRIBUTION: MAX < MIN	
You called the uniform(min, max) function with max < min		
53	TRIANGULAR DISTRIBUTION: PARAMETER ERROR	
	In a call to triangular(min, max, mode) either min < max or mode < min or mode > max	
54	GAMMA DISTRIBUTION: PARAMETER ERROR	
In a call to gamma(mean, stddev), either mean <= 0.0 or stddev <= 0.0.		
55	EXPONENTIAL DISTRIBUTION: MEAN < 0.0	
In a	call to exponential(mean), mean <= 0.0	
56	ERLANG2 DISTRIBUTION: PARAMETER ERROR	
In a call to erlang2(mean, stddev), either mean <= 0.0 or stddev <= 0.0 or stddev >= mean		
57	HYPERX DISTRIBUTION: VARIANCE <= MEAN*MEAN	
In a	call to hyperx(mean, var), var <= mean <sup>2</sup>	
58	BETA DISTRIBUTION: PARAMETER ERROR	
In a call to beta(min, max, shape1, shape2), either max <= min or shape1 <= 0.0 or shape2 <= 0.0		
59	WEIBULL DISTRIBUTION: PARAMETER ERROR	
In a call to weibull(shape, scale), either shape <= 0.0 or scale <= 0.0		
60	LOGNORMAL DISTRIBUTION: MEAN <= 0.0	
In a call to lognormal(mean, stddev), mean <= 0.0		
61	CAUCHY DISTRIBUTION: XBETA <= 0.0	

In a call to cauchy(alpha, beta), beta <= 0.0		
62	UNIFORM_INT DISTRIBUTION: MAX < MIN	
In a call to uniform_int(min, max), max < min		
63	BERNOULLI DISTR.: PROB. SUCCESS < 0.0 OR > 1.0	
In a call to bernoulli(probSuccess), either probSuccess < 0.0 or probSuccess > 1.0		

64	BINOMIAL DISTRIBUTION: PARAMETER ERROR
In a call to binomial(probSuccess, numTrials), either probSuccess <= 0.0 or probSuccess >= 1.0 or numTrials < 1	
65	GEOMETRIC DISTR.: PROB. SUCCESS <= 0.0 OR >= 1.0
In a call to geometric(probSuccess), either probSuccess <= 0.0 or probSuccess >= 1.0	
66	NEG. BINOMIAL DISTRIBUTION: PARAMETER ERROR
In a call to negative_binomial(successNum, probSuccess) either successNum <= 0.0 or probSuccess <= 0.0 or probSuccess >= 1.0	
67	POISSON DISTRIBUTION: MEAN <= 0.0
In a call to poisson(mean), mean <= 0.0	
68	(NOT USED)
69	(NOT USED)

70	BUFFER: ERROR IN DELETE_BUFFER	
In a call to delete_buffer(bfr), bfr is NIL		
71	BUFFER: REMOVE_SPACE ERROR	
In a call to buffer_remove_space(bft, amt), amt is greater than the amount of space in the buffer		
72	(NOT USED)	

73	TOO MANY BUFFERS		
	Tried to too many buffers; either reduce the number of buffers created or increase max_buffers		
74	STORAGE: REMOVE ERROR		
In a call to remove_store(store, size), either size exceeds the amount of storage currently available or the original amount of storage			
75	PARETO DISTRIBUTION: PARAMETER <= 0.0		
In a	call to pareto(a), a <= 0.0		
76	SETUP_EMPIRICAL – ERROR IN PROB. ARRAY		
In a call to setup_empirical, the sum of the probabilities specified is not equal to 1.0			
77	RUN_LENGTH: ACCURACY MUST BE > 0.0 AND < 1.0		
In a call to table_run_length or qtable_run_length, either accuracy <= 0.0 or accuracy >= 1.0			
78	RUN_LENGTH: CPU MAX MUST BE > 0.0		

In a call to table_run_length or qtable_run_length, the maximum cpu time specification is <= 0.0	
79 NEXT-EVENT-LIST ERROR: TIME GOING BACKWARDS	
An error has occurred in the routines that manage the next_event_list; please contact Mesquite Software, Inc.	
80 TRIED TO DELETE EMPTY MAILBOX SET	
In a call to delete_mailbox_set, the pointer is NIL	
81 TRIED TO RECEIVE ON EMPTY MAILBOX SET	
In a call to receive_any, the pointer is invalid	
82 TIMED_PUT (BUFFER): NEGATIVE TIME-OUT	
In a call to buffer_timed_put, the timeout interval is negative	
83 TIMED_GET (BUFFER): NEGATIVE TIME OUT	
In a call to buffer_timed_get, the timeout interval is negative	
84 STORAGE: ALLOCATE OR DEALLOCATE NEG. AMT	
In a call to allocate, alloc, deallocate, dealloc, timed_allocate or timed_alloc, passed an amount which is negative	

# 23. Acknowledgments

- Teemu Kerola assisted in the initial implementation of CSIM. He also designed and implemented the MONIT event logging feature and the post-run analysis program for the SUN.
- Bill Alexander has provided consultation on the wisdom of many proposed features.
- Leonard Cohn suggested using mailboxes.
- Ed Rafalko, of Eastman Kodak, provided the changes required to have CSIM available on the VMS operating system.
- Rich Lary and Harry Siegler of DEC have provided code for the VMS version of CSIM. They also suggested a number of modifications which have improved the performance of CSIM programs.
- Geoff Brown of Cornell University did most of the work for the HP-300 version. He also provided the note on CSIM on the NeXT System.
- Jeff Brumfield, of The University of Texas at Austin, critiqued many aspects CSIM. He and Kerola suggested process classes.
- Connie Smith, of L & S Systems, did much of the work on the Macintosh version.
- Kevin Wilkinson, of HP Labs, did most of the work on the HP Prism support.
- Murthy Devarakonda, of IBM T.J. Watson Research Labs, did most of the work on the IBM RS/6000 support.

## 23. Acknowledgments

- Jeff Brumfield provided the ideas, code, and documentation on meters, boxes, confidence intervals, and run length control. He also improved the format of the output reports and added the additional probability distributions.
- Beth Tobias rewrote the CSIM manual.
- Jorge Gonzales helped test and debug CSIM18.
- Dawn Childress revised and reformatted the CSIM18 manuals.

# 24. List of References

[Brow88] Brown, R., Calendar Queues: A Fast O(1) Priority

Queue Implementation for the Simulation Event Set Problem, *Communications of the ACM*, (31, 10),

October, 1988, pp. 1220 - 1227.

KeSc87] Kerola, T. and H. Schwetman, Monit: A Performance

Monitoring Tool for Parallel and Pseudo-Parallel

Programs, Proceedings of the 1987 ACM

SIGMETRICS Conference on Measurement and

Modeling of Computer Systems,

ACM/SIGMETRICS, May, 1987, pp. 163-174.

[Lake91] Law, A. and D. Kelton, Simulation Modeling and

Analysis, second edition, (McGraw-Hill, 1991).

[MaMc73] MacDougall, M.H. and J.S. McAlpine, Computer

System Simulation with ASPOL, Symposium on the Simulation of Computer Systems, ACM/SIGSIM,

June, 1973, pp. 93-103.

[MacD74] MacDougall, M.H., Simulating the NASA Mass Data

Storage Facility, *Symposium on the Simulation of Computer Systems*, ACM/SIGSIM, June 1974, pp.

33-43.

.[MacD75] MacDougall, M.H., Process and Event Control in

ASPOL, Symposium on the Simulation of Computer Systems, ACM/SIGSIM, August, 1975, pp. 39-51.

#### 24. List of References

[Schw86]	Schwetman, H.D., CSIM: A C-Based, Process-Oriented Simulation Language, <i>Proceedings of the 1986 Winter Simulation Conference</i> , December, 1986, pp. 387 - 396.
[Schw88]	Schwetman, H.D., Using CSIM to Model Complex Systems, <i>Proceedings of the 1988 Winter</i> <i>Simulation Conference</i> , December, 1988, pp. 246 - 253; also available as Microelectronics and Computer Technology Corporation, Technical Report ACA-ST-154-88.
[Schw90b]	Schwetman, H.D., Introduction to Process-Oriented Simulation and CSIM, <i>Proceedings of the 1990 Winter Simulation Conference</i> , December, 1990, pp. 154- 157.
[Schw94]	Schwetman, H.D., CSIM17: A Simulation Model- Building Toolkit, Proceedings of the 1994 Winter Simulation Conference, December, 1994. pp. 464- 470
[Schw95]	Schwetman, H.D., Object-Oriented Simulation Modeling with C++/CSIM17, Proceeding of the 1995 Winter Simulation Conference, December, 1995.
[Schw96]	Schwetman, H.D., CSIM18 - The Simulation Engine, Proceedings of the 1996 Winter Simulation Conference, December 1996.
[Schw97]	Schwetman, H.D., Data Analysis and Automatic Run Length Control in CSIM18, Proceedings of the 1997 Winter Simulation Conference, Atlanta, GA, Dec. 1997

#### 24. List of References

[Schw98]	Schwetman, H.D., Model-Based Systems Analysis Using CSIM18, Proceedings of the 1998 Winter Simulation Conference, Washington, DC, Dec. 1998
[Schw99]	Schwetman, H.D., Model, Then Build: A Modern Approach to Systems Development Using CSIM18, Proceedings of the 1999 Winter Simulation Conference, Phoenix, AZ, Dec., 1999
[Schw00a]	Schwetman, H.D., Finding the Best System Configuration: An Application of Simulation and Optimization, Proceedings of the 2000 European Simulation Multiconference, Gent, Belgium, May 2000 (Society for Computer Simulation)
[Schw00b]	Schwetman, H.D., Optimizing Simulations with CSIM18/OptQuest: Finding the Best Configuration, Proceedings 2000 Winter Simulation Conference, Orlando, FL, Dec., 2000
[Schw01]	Schwetman, H.D., CSIM19: A Powerful Tool For Building Systems Models, Proceedings 2001 Winter Simulation Conference, Washington, DC, Dec. 2001

#### 24. List of References

A sample CSIM program follows. This program is a model of an M/M/1 queueing system. The process *sim* includes a *for* loop, which generates, at appropriate intervals (exponentially distributed with mean IATM) arriving customers. These customers contend for the facility on a first-come-first-served basis. As each customer gains exclusive use of the facility, they delay for a service period (again exponentially distributed, but with mean SVTM) and then depart. The individual response times (time of arrival to time of departure) are collected in a table. The program also makes use of the histogram feature to collect the frequency distribution of the queue length.

#### Sample Program to Simulate Single Server Facility

```
/* simulate an M/M/1 queue
 (an open queue with exponential service times and interarrival intervals)
#include csim.h
#include <stdio.h>
#define SVTM 1.0
                          /* mean of service time distribution */
                 2.0
#define IATM
                               /* mean of inter-arrival time distribution */
#define NARS
                 5000 /* number of arrivals to be simulated*/
FACILITY f:
                          /* pointer for facility */
EVENT done:
                          /* pointer for counter */
TABLE tbl;
                          /* pointer for table */
QTABLE qtbl;
                      /* pointer for ghistogram */
```

```
int cnt;
                       /* number of active tasks*/
FILE *fp;
void init();
void generateCustomers();
void cust();
void sim()
                            /* 1st process - named sim */
    init();
                            /* initialize file, model */
    create(sim);
                       /* required create statement */
    generateCustomers();/* invoke process to generate customers */
    wait(done);
                            /* wait until all done */
    report():
                            /* print report */
    mdlstat();
                            /* print operational statistics */
}
void generateCustomers()
    int i;
                            /* create statement */
    create(gen);
    for(i = 1; i \le NARS; i++) 
         hold(exponential(IATM)); /* hold interarrival */
                                      /* initiate process cust */
         cust();
    }
void cust()
                            /* process customer */
    TIME t1;
                       /* create statement */
    create(cust);
                            /* time of arrival */
    t1 = clock;
                            /* note arrival */
    note_entry(qtbl);
    reserve(f);
                            /* reserve facility f */
    hold(exponential(SVTM));/* hold service time */
                            /* release facility f */
    release(f):
    record(clock-t1, tbl); /* record response time */
```

```
/* note departure */
     note_exit(qtbl);
                            /* decrement cnt */
     cnt--;
     if(cnt == 0)
         set(done);
                                 /*if last arrival, signal done*/
void init()
     fp = fopen(csim.out, w);
     set_output_file(fp);
     set_trace_file(fp);
     set_error_file(fp);
     set_model_name(M/M/1 Queue);
     f = facility(facility);
                                 /* initialize facility */
     done = event(done);
                                      /* initialize event */
     tbl = table(resp tms);
                                      /* initialize table */
     qtbl = qhistogram(num in sys, 10l); /* initialize qhistogram */
                                      /* initialize cnt */
     cnt = NARS;
```

# 26. Statements, Reserved Words

## 26.1 Statement and Reserved Words

Usage	Object	Section
<pre>add_more_store(STORE, long);</pre>	storage	5.9
add_store(long, STORE);	storage	5.9
alloc(STORE, long);	storage	5.2
allocate(long, STORE);	storage	5.2
avail(STORE);	storage	5.12
bernoulli(ps)	random	18.1
beta(mn, mx, sh1, sh2)	random	18.1
binomial(ps,nt)	random	18.1
box(name)	box	14.1
box_name(BOX);	box	14.7
<pre>box_number_confidence(BOX);</pre>	box	14.7
<pre>box_number_histogram(BOX, long, long, long);</pre>	box	14.7
<pre>box_number_moving_window(BOX, long);</pre>	box	14.6
<pre>box_number_qtable(BOX);</pre>	box	14.7
<pre>box_number_run_length(BOX, double, double, double);</pre>	box	14.5
<pre>box_summary();</pre>	box	14.3

20. Neserved Words		
<pre>box_time_confidence(BOX);</pre>	box	14.7
<pre>box_time_histogram(BOX, long, double, double);</pre>	box	14.4
<pre>box_time_moving_window(BOX, long);</pre>	box	14.6
<pre>box_time_run_length(BOX, double, double, double);</pre>	box	14.5
<pre>box_time_table(BOX);</pre>	box	14.7
buffer(name, size)	buffer	6.1
<pre>buffer_add_space(BUFFER b, const long amt);</pre>	buffer	6.7
<pre>buffer_current(BUFFER b);</pre>	buffer	6.1
<pre>buffer_get(BUFFER b, const long amt);</pre>	buffer	6.3
<pre>buffer_get_count(BUFFER b);</pre>	buffer	6.7
<pre>buffer_get_current_count(BUFFER b);</pre>	buffer	6.7
<pre>buffer_get_first_process(BUFFER b);</pre>	buffer	9.4
<pre>buffer_get_insert_process(BUFFER b, PROCESS_PTR p);</pre>	buffer	9.4
<pre>buffer_get_last_process(BUFFER b);</pre>	buffer	9.4
<pre>buffer_get_remove_process(BUFFER b, PROCESS_PTR p);</pre>	buffer	9.4
<pre>buffer_get_timeQueue(BUFFER b);</pre>	buffer	6.1
<pre>buffer_get_total(BUFFER b);</pre>	buffer	6.1
<pre>buffer_name(BUFFER b);</pre>	buffer	6.1
<pre>buffer_put(BUFFER b, const long amt);</pre>	buffer	6.2
<pre>buffer_put_count(BUFFER b);</pre>	buffer	6.1
<pre>buffer_put_current_count(BUFFER b);</pre>	buffer	6.1
<pre>buffer_put_first_process(BUFFER b);</pre>	buffer	9.4
<pre>buffer_put_insert_process(BUFFER b, PROCESS_PTR p);</pre>	buffer	9.4
<pre>buffer_put_last_process(BUFFER b);</pre>	buffer	9.4
buffer_put_remove_process(BUFFER b, PROCESS_PTR	buffer	9.4

		<u> </u>
p);		
<pre>buffer_put_timeQueue(BUFFER b);</pre>	buffer	6.1
<pre>buffer_put_total(BUFFER b);</pre>	buffer	6.1
<pre>buffer_remove_space(BUFFER b, const long amt);</pre>	buffer	6.8
<pre>buffer_size(BUFFER b);</pre>	buffer	6.1
<pre>buffer_timed_get(BUFFER b, const long amt, const double t);</pre>	buffer	6.6
<pre>buffer_timed_put(BUFFER b, const long amt, const double t);</pre>	buffer	6.6
cauchy(alpha,beta)	random	18.1
class_cnt(CLASS);	process_class	17.7
class_completions(FACILITY, CLASS);	facility	4.14
class_holdcnt(CLASS);	process_class	17.7
class_holdtime(CLASS);	process_class	17.7
class_id(CLASS);	process_class	17.7
class_lifetime(CLASS);	process_class	17.7
class_name(CLASS);	process_class	17.7
class_qlen(FACILITY, CLASS);	facility	4.14
class_qlength(FACILITY, CLASS);	facility	4.14
<pre>class_resp(FACILITY, CLASS);</pre>	facility	4.14
<pre>class_serv(FACILITY, CLASS);</pre>	facility	4.14
class_tput(FACILITY, CLASS);	facility	4.14
class_util(FACILITY, CLASS);	facility	4.14
clear(ev)	event	7.7
<pre>clear_err_handler();</pre>	utility	21.5
clock()	utility	21.5
<pre>collect_class_facility(FACILITY);</pre>	facility	4.13
collect_class_facility_all();	facility	4.13
L		

completions(FACILITY);	facility	4.14
<pre>conclude_csim();</pre>	utility	21.3
cputime();	utility	21.1
<pre>create(const char*);</pre>	process	3.2
<pre>create_box(const char*);</pre>	box	14.1
<pre>create_buffer(const char *nm, const long sz);</pre>	buffer	6.1
<pre>create_event (const char*);</pre>	event	7.1
<pre>create_event_set(EVENT*, const char*, long);</pre>	event	7.12
<pre>create_facility(const char*);</pre>	facility	4.1
<pre>create_facility_ms(const char*, long);</pre>	facility	4.1
<pre>create_facility_set(FACILITY*, const char*, long);</pre>	facility	4.8
<pre>create_global_event(const char*);</pre>	event	7.1
<pre>create_global_mailbox(const char*);</pre>	mailbox	8.1
<pre>create_mailbox(const char*);</pre>	mailbox	8.1
<pre>create_mailbox_set(MBOX*, const char*, long);</pre>	mailbox	8.9
<pre>create_meter(const char*);</pre>	meter	13.1
<pre>create_permanent_table(const char*);</pre>	table	11.1
<pre>create_process_class(const char*);</pre>	process_class	17.1
<pre>create_process_class_perm(const char*);</pre>	process_class	17.1
<pre>create_qtable(const char*);</pre>	qtable	12.1
<pre>create_storage(const char*, long);</pre>	storage	5.1
<pre>create_storage_set(STORE*, const char*, long, long);</pre>	storage	5.6
<pre>create_stream();</pre>	random	18.1
<pre>create_table(const char*);</pre>	table	11.1
csim_clear(EVENT);	event	7.7
<pre>csim_error_msg(long);</pre>	utility	21.5

csim_identity(); csim_priority(); csim_priority(); csim_queue(EVENT); event 7.4 csim_random(x,y) csim_random(x,y) csim_random_int(mn,mx) csim_receive(MBOX, long*); csim_receive(MBOX, long*); desim_reset(); csim_send(MBOX, long); csim_send(MBOX, long); csim_set(EVENT); event 7.6 csim_state(EVENT); event 7.13 csim_status(FACILITY); desim_terminate(); current_class(); current_state(QTABLE); dealloc(STORE, long); deallocate(long, STORE); delete_buffer(BUFFER b); delete_event_set(EVENT*); delete_event_set(EVENT*); delete_facility(FACILITY); delete_facility(FACILITY); delete_facility(FACILITY); delete_facility(FACILITY); delete_facility(FACILITY); delete_facility(FACILITY); delete_facility(FACILITY); delete_facility(FACILITY); delete_facility_set(FACILITY*); delete_mailbox(MBOX); mailbox 8.11		201 110001100 11010	<u> </u>
csim_priority();         process         3.6           csim_queue(EVENT);         event         7.4           csim_random(x,y)         random         18.1           csim_random_int(mn,mx)         random         18.1           csim_receive(MBOX, long*);         mailbox         8.3           csim_receive(MBOX, long*);         utility         21.4           csim_reset();         utility         21.4           csim_send(MBOX, long);         mailbox         6.2           csim_set(EVENT);         event         7.6           csim_set(EVENT);         event         7.13           csim_status(FACILITY);         facility         4.14           csim_terminate();         utility         3.4           csim_terminate();         utility         3.4           csim_terminate();         utility         3.4           csim_status(FACILITY);         event         7.2           current_class();         process_class         17.2           current_class();         gtable         12.7           dealloc(STORE, long);         storage         5.3           dealloc(STORE, long);         storage         5.3           delete_box(BOX);         box         5.11 <tr< td=""><td><pre>csim_exit(long);</pre></td><td>utility</td><td>21.3</td></tr<>	<pre>csim_exit(long);</pre>	utility	21.3
csim_queue(EVENT);         event         7.4           csim_random(x,y)         random         18.1           csim_random_int(mn,mx)         random         18.1           csim_receive(MBOX, long*);         mailbox         8.3           csim_rerun();         utility         21.4           csim_reset();         utility         21.4           csim_resed(MBOX, long);         mailbox         6.2           csim_send(MBOX, long);         event         7.6           csim_set(EVENT);         event         7.6           csim_state(EVENT);         event         7.13           csim_status(FACILITY);         facility         4.14           csim_terminate();         utility         3.4           csim_wait(EVENT);         event         7.2           current_class();         process_class         17.2           current_state(QTABLE);         qtable         12.7           dealloc(STORE, long);         storage         5.3           delete_box(BOX);         box         5.11           delete_buffer(BUFFER b);         buffer         6.9           delete_event_set(EVENT*);         event         7.9           delete_event_set(EVENT*);         event         7.9 <td><pre>csim_identity();</pre></td> <td>process</td> <td>3.6</td>	<pre>csim_identity();</pre>	process	3.6
csim_random(x,y)       random       18.1         csim_random_int(mn,mx)       random       18.1         csim_receive(MBOX, long*);       mailbox       8.3         csim_rerun();       utility       21.4         csim_reset();       utility       21.4         csim_send(MBOX, long);       mailbox       6.2         csim_set(EVENT);       event       7.6         csim_state(EVENT);       event       7.13         csim_status(FACILITY);       facility       4.14         csim_terminate();       utility       3.4         csim_wait(EVENT);       event       7.2         current_class();       process_class       17.2         current_state(QTABLE);       qtable       12.7         dealloc(STORE, long);       storage       5.3         deallocate(long, STORE);       storage       5.3         delete_buffer(BUFFER b);       box       5.11         delete_event(EVENT);       event       7.9         delete_event_set(EVENT*);       event       7.9         delete_facility(FACILITY);       facility       4.12         delete_facility_set(FACILITY*);       facility       4.12         delete_mailbox(MBOX);       mailbox       8	<pre>csim_priority();</pre>	process	3.6
csim_random_int(mn,mx)         random         18.1           csim_receive(MBOX, long*);         mailbox         8.3           csim_rerun();         utility         21.4           csim_reset();         utility         21.4           csim_send(MBOX, long);         mailbox         6.2           csim_set(EVENT);         event         7.6           csim_state(EVENT);         event         7.13           csim_status(FACILITY);         facility         4.14           csim_terminate();         utility         3.4           csim_wait(EVENT);         event         7.2           current_class();         process_class         17.2           current_state(QTABLE);         qtable         12.7           dealloc(STORE, long);         storage         5.3           deallocate(long, STORE);         storage         5.3           delete_box(BOX);         box         5.11           delete_event_set(EVENT*);         event         7.9           delete_event_set(EVENT*);         event         7.9           delete_facility(FACILITY);         facility         4.12           delete_facility_set(FACILITY*);         facility         4.12           delete_mailbox(MBOX);         mailbox	csim_queue(EVENT);	event	7.4
csim_receive(MBOX, long*); csim_rerun(); csim_rerun(); csim_reset(); dutility 21.4 csim_reset(); dutility 21.4 csim_send(MBOX, long); devent csim_set(EVENT); event csim_state(EVENT); event csim_status(FACILITY); facility 4.14 csim_terminate(); dutility 3.4 csim_wait(EVENT); event 7.2 current_class(); current_state(QTABLE); dealloc(STORE, long); deallocate(long, STORE); delete_box(BOX); delete_box(BOX); delete_event(EVENT); delete_event(EVENT); event 7.9 delete_event_set(EVENT*); event 7.9 delete_facility(FACILITY); delete_facility_set(FACILITY*); delete_mailbox(MBOX); mailbox 8.11	csim_random(x,y)	random	18.1
csim_rerun(); csim_reset(); utility 21.4 csim_send(MBOX, long); mailbox 6.2 csim_set(EVENT); event 7.6 csim_state(EVENT); event 7.13 csim_status(FACILITY); facility 4.14 csim_terminate(); utility 3.4 csim_wait(EVENT); event 7.2 current_class(); process_class 17.2 current_state(QTABLE); dealloc(STORE, long); deallocate(long, STORE); delete_box(BOX); delete_box(BOX); delete_event(EVENT); delete_event(EVENT); event 7.9 delete_event_set(EVENT*); delete_facility(FACILITY); delete_facility_set(FACILITY*); delete_mailbox(MBOX); mailbox 8.11	csim_random_int(mn,mx)	random	18.1
csim_reset();         utility         21.4           csim_send(MBOX, long);         mailbox         6.2           csim_set(EVENT);         event         7.6           csim_state(EVENT);         event         7.13           csim_status(FACILITY);         facility         4.14           csim_terminate();         utility         3.4           csim_wait(EVENT);         event         7.2           current_class();         process_class         17.2           current_state(QTABLE);         qtable         12.7           dealloc(STORE, long);         storage         5.3           deallocate(long, STORE);         storage         5.3           delete_box(BOX);         box         5.11           delete_event(EVENT);         event         7.9           delete_event_set(EVENT*);         event         7.9           delete_facility(FACILITY);         facility         4.12           delete_mailbox(MBOX);         mailbox         8.11	csim_receive(MBOX, long*);	mailbox	8.3
csim_send(MBOX, long); csim_set(EVENT); event 7.6  csim_state(EVENT); event 7.13  csim_status(FACILITY); facility 4.14  csim_terminate(); utility 3.4  csim_wait(EVENT); event 7.2  current_class(); process_class 17.2  current_state(QTABLE); dealloc(STORE, long); deallocate(long, STORE); delete_box(BOX); box 5.11  delete_buffer(BUFFER b); delete_event(EVENT); event 7.9  delete_event_set(EVENT*); event 7.9  delete_facility(FACILITY); delete_facility_set(FACILITY*); delete_mailbox(MBOX); mailbox 8.11	csim_rerun();	utility	21.4
csim_set(EVENT); event 7.6  csim_state(EVENT); event 7.13  csim_status(FACILITY); facility 4.14  csim_terminate(); utility 3.4  csim_wait(EVENT); event 7.2  current_class(); process_class 17.2  current_state(QTABLE); qtable 12.7  dealloc(STORE, long); storage 5.3  deallocate(long, STORE); storage 5.3  delete_box(BOX); box 5.11  delete_buffer(BUFFER b); buffer 6.9  delete_event(EVENT); event 7.9  delete_event_set(EVENT*); event 7.9  delete_facility(FACILITY); facility 4.12  delete_mailbox(MBOX); mailbox 8.11	<pre>csim_reset();</pre>	utility	21.4
csim_state(EVENT); event 7.13  csim_status(FACILITY); facility 4.14  csim_terminate(); utility 3.4  csim_wait(EVENT); event 7.2  current_class(); process_class 17.2  current_state(QTABLE); qtable 12.7  dealloc(STORE, long); storage 5.3  deallocate(long, STORE); storage 5.3  delete_box(BOX); box 5.11  delete_buffer(BUFFER b); buffer 6.9  delete_event(EVENT); event 7.9  delete_event_set(EVENT*); event 7.9  delete_facility(FACILITY); facility 4.12  delete_mailbox(MBOX); mailbox 8.11	csim_send(MBOX, long);	mailbox	6.2
csim_status(FACILITY); facility 4.14  csim_terminate(); utility 3.4  csim_wait(EVENT); event 7.2  current_class(); process_class 17.2  current_state(QTABLE); qtable 12.7  dealloc(STORE, long); storage 5.3  deallocate(long, STORE); box 5.11  delete_box(BOX); box 5.11  delete_buffer(BUFFER b); buffer 6.9  delete_event(EVENT); event 7.9  delete_event_set(EVENT*); event 7.9  delete_facility(FACILITY); facility 4.12  delete_mailbox(MBOX); mailbox 8.11	csim_set(EVENT);	event	7.6
csim_terminate(); csim_wait(EVENT); event 7.2  current_class(); current_state(QTABLE); dealloc(STORE, long); deallocate(long, STORE); delete_box(BOX); delete_buffer(BUFFER b); delete_event(EVENT); delete_event_set(EVENT*); delete_facility(FACILITY*); delete_mailbox(MBOX); mailbox  8.11	csim_state(EVENT);	event	7.13
<pre>csim_wait(EVENT);</pre>	csim_status(FACILITY);	facility	4.14
<pre>current_class(); current_state(QTABLE); dealloc(STORE, long); deallocate(long, STORE); delete_box(BOX); delete_buffer(BUFFER b); delete_event(EVENT); delete_event_set(EVENT*); delete_facility(FACILITY); delete_facility_set(FACILITY*); delete_mailbox(MBOX);</pre> process_class 17.2  qtable 12.7  destorage 5.3  box 5.11  buffer 6.9  event 7.9  delete_event 7.9  delete_event 4.12  delete_facility_set(FACILITY*); facility 4.12  delete_mailbox(MBOX); mailbox 8.11	csim_terminate();	utility	3.4
<pre>current_state(QTABLE); dealloc(STORE, long); deallocate(long, STORE); delete_box(BOX); delete_buffer(BUFFER b); delete_event(EVENT); delete_event_set(EVENT*); delete_facility(FACILITY); delete_facility_set(FACILITY*); delete_mailbox(MBOX);</pre> <pre>gtable qtable 12.7  gtable 12.7  feelete_box(BOX); for a color of the colo</pre>	csim_wait(EVENT);	event	7.2
dealloc(STORE, long); storage 5.3  deallocate(long, STORE); storage 5.3  delete_box(BOX); box 5.11  delete_buffer(BUFFER b); buffer 6.9  delete_event(EVENT); event 7.9  delete_event_set(EVENT*); event 7.9  delete_facility(FACILITY); facility 4.12  delete_facility_set(FACILITY*); facility 4.12  delete_mailbox(MBOX); mailbox 8.11	<pre>current_class();</pre>	process_class	17.2
deallocate(long, STORE); storage 5.3  delete_box(BOX); box 5.11  delete_buffer(BUFFER b); buffer 6.9  delete_event(EVENT); event 7.9  delete_event_set(EVENT*); event 7.9  delete_facility(FACILITY); facility 4.12  delete_facility_set(FACILITY*); facility 4.12  delete_mailbox(MBOX); mailbox 8.11	<pre>current_state(QTABLE);</pre>	qtable	12.7
<pre>delete_box(BOX);</pre>	dealloc(STORE, long);	storage	5.3
<pre>delete_buffer(BUFFER b);     delete_event(EVENT);     delete_event_set(EVENT*);     delete_facility(FACILITY);     delete_facility_set(FACILITY*);     delete_mailbox(MBOX);     buffer     6.9     7.9     event     7.9     delete_facility (FACILITY);     facility     4.12     delete_mailbox(MBOX);</pre>	<pre>deallocate(long, STORE);</pre>	storage	5.3
delete_event(EVENT);event7.9delete_event_set(EVENT*);event7.9delete_facility(FACILITY);facility4.12delete_facility_set(FACILITY*);facility4.12delete_mailbox(MBOX);mailbox8.11	<pre>delete_box(BOX);</pre>	box	5.11
delete_event_set(EVENT*);event7.9delete_facility(FACILITY);facility4.12delete_facility_set(FACILITY*);facility4.12delete_mailbox(MBOX);mailbox8.11	<pre>delete_buffer(BUFFER b);</pre>	buffer	6.9
delete_facility(FACILITY);facility4.12delete_facility_set(FACILITY*);facility4.12delete_mailbox(MBOX);mailbox8.11	<pre>delete_event(EVENT);</pre>	event	7.9
delete_facility_set(FACILITY*); facility 4.12 delete_mailbox(MBOX); mailbox 8.11	<pre>delete_event_set(EVENT*);</pre>	event	7.9
delete_mailbox(MBOX); mailbox 8.11	<pre>delete_facility(FACILITY);</pre>	facility	4.12
	<pre>delete_facility_set(FACILITY*);</pre>	facility	4.12
1.1. (VPOVE)	<pre>delete_mailbox(MBOX);</pre>	mailbox	8.11
delete_mailbox_set(MBOX*);   mailbox   8.11	<pre>delete_mailbox_set(MBOX*);</pre>	mailbox	8.11

Zu. Negerveu vvorug		
<pre>delete_meter(METER);</pre>	meter	13.1
delete_process_class(CLASS);	process_class	17.6
<pre>delete_qtable(QTABLE);</pre>	qtable	12.1
<pre>delete_storage(STORE);</pre>	storage	5.11
<pre>delete_storage_set(STORE*);</pre>	storage	5.11
<pre>delete_table(TABLE);</pre>	table	11.1
<pre>dump_status();</pre>	utility	19.4
empirical(n,cut,als,val)	random	18.1
<pre>enter_box(BOX);</pre>	box	14.2
erlang(mean,var)	random	18.1
erlang2(mean,var)	random	18.1
erlangn(mean,n)	random	18.1
event(name)	event	7.1
event_first_queue_process(EVENT);	event	9.5
event_first_wait_process(EVENT);	event	9.5
<pre>event_insert_queue_process(EVENT, PROCESS_PTR);</pre>	event	9.5
<pre>event_insert_wait_process(EVENT, PROCESS_PTR);</pre>	event	9.5
event_last_queue_process(EVENT);	event	9.5
event_last_wait_process(EVENT);	event	9.5
<pre>event_monitor(EVENT ev);</pre>	event	7.1
event_name(EVENT);	event	7.13
<pre>event_qlen(EVENT);</pre>	event	7.13
event_queue_count(EVENT ev);	event	7.13
<pre>event_queue_delay_count(EVENT ev);</pre>	event	7.13
<pre>event_queue_length(EVENT ev);</pre>	event	7.13
event_queue_sum(EVENT ev);	event	7.13
event_queue_time(EVENT ev);	event	7.13
	i e	1

	201 110001100 11010	
<pre>event_remove_queue_process(EVENT, PROCESS_PTR);</pre>	event	9.5
<pre>event_remove_wait_process(EVENT, PROCESS_PTR);</pre>	event	9.5
event_set(arr,name,n)	event	7.1
event_set_count(EVENT ev);	event	7.13
<pre>event_set_monitor(EVENT *evs);</pre>	event	7.1
<pre>event_set_name(EVENT*);</pre>	event	7.13
event_wait_count(EVENT ev);	event	7.13
event_wait_delay_count(EVENT ev);	event	7.13
event_wait_length(EVENT ev);	event	7.13
event_wait_sum(EVENT ev);	event	7.13
event_wait_time(EVENT ev);	event	7.13
events_processed();	utility	19.2.3
exit_box(BOX, double);	box	14.2
expntl(mean)	random	18.1
exponential(mean)	random	18.1
facility(name)	facility	4.1
<pre>facility_first_process(FACILITY);</pre>	facility	9.2
<pre>facility_insert_process(FACILITY, PROCESS_PTR);</pre>	facility	9.2
<pre>facility_last_process(FACILITY);</pre>	facility	9.2
facility_ms(name,num)	facility	4.7
<pre>facility_name(FACILITY);</pre>	facility	4.14
<pre>facility_remove_process(FACILITY, PROCESS_PTR);</pre>	facility	9.2
facility_set(arr,name,len)	facility	4.8
fcfs(FACILITY, double);	facility	4.11
fcfs_sy(FACILITY, double);	facility	4.11
gamma(mean,stddev)	random	18.1
geometric(ps)	random	18.1
L	1	

ZO. NESCIVEU WOIUS		
<pre>get_process_identity(PROCESS_PTR);</pre>	process	9.1
<pre>get_process_name(PROCESS_PTR);</pre>	process	9.1
<pre>get_process_priority(PROCESS_PTR);</pre>	process	9.1
<pre>get_process_struct(PROCESS_PTR);</pre>	process	9.1
<pre>get_this_struct();</pre>	process	9.1
global_event(name)	event	7.1
global_mailbox(name)	mailbox	8.1
hold(double);	process	3.3
hyperx(mean,var)	random	18.1
hypoexponential(mn,vr)	random	18.1
identity()	process	3.6
<pre>inf_srv(FACILITY, double);</pre>	facility	4.11
<pre>lcfs_pr(FACILITY, double);</pre>	facility	4.11
lognormal(mean,stddev)	random	18.1
mailbox(name)	mailbox	8.1
<pre>mailbox_first_msg(MBOX);</pre>	mailbox	9.6
<pre>mailbox_first_process(MBOX);</pre>	mailbox	9.6
<pre>mailbox_insert_msg(MBOX, MSG_PTR);</pre>	mailbox	9.6
<pre>mailbox_insert_process(MBOX, PROCESS_PTR);</pre>	mailbox	9.6
<pre>mailbox_last_msg(MBOX);</pre>	mailbox	9.6
<pre>mailbox_last_process(MBOX);</pre>	mailbox	9.6
<pre>mailbox_monitor(MBOX);</pre>	mailbox	8.7
<pre>mailbox_msg_count(MBOX);</pre>	mailbox	8.12
<pre>mailbox_msg_delay_count(MBOX);</pre>	mailbox	8.12
<pre>mailbox_msg_length(MBOX);</pre>	mailbox	8.12
<pre>mailbox_msg_sum(MBOX);</pre>	mailbox	8.12
<pre>mailbox_msg_time(MBOX);</pre>	mailbox	8.12
	1	1

	<b>201 110001100 110</b>	
<pre>mailbox_name(MBOX);</pre>	mailbox	8.12
<pre>mailbox_proc_count(MBOX);</pre>	mailbox	8.12
<pre>mailbox_proc_delay_count(MBOX);</pre>	mailbox	8.12
<pre>mailbox_proc_length(MBOX);</pre>	mailbox	8.12
<pre>mailbox_proc_sum(MBOX);</pre>	mailbox	8.12
<pre>mailbox_proc_time(MBOX);</pre>	mailbox	8.12
<pre>mailbox_queue_cnt(MBOX);</pre>	mailbox	8.12
<pre>mailbox_remove_msg(MBOX, MSG_PTR);</pre>	mailbox	9.6
<pre>mailbox_remove_process(MBOX, PROCESS_PTR);</pre>	mailbox	9.6
mailbox_set(arr,name,n)	mailbox	8.1
<pre>mailbox_set_monitor(MBOX*);</pre>	mailbox	8.7
<pre>mailbox_set_name(MBOX*);</pre>	mailbox	8.10
<pre>mailbox_set_num_msgs(MBOX*);</pre>	mailbox	8.12
<pre>max_buffers(long);</pre>	utility	21.2
<pre>max_classes(long);</pre>	utility	21.2
<pre>max_events(long);</pre>	utility	21.2
<pre>max_facilities(long);</pre>	utility	21.2
<pre>max_histograms(long);</pre>	utility	21.2
<pre>max_mailboxes(long);</pre>	utility	21.2
<pre>max_messages(long);</pre>	utility	21.2
<pre>max_processes(long);</pre>	utility	21.2
<pre>max_qtables(long);</pre>	utility	21.2
<pre>max_servers(long);</pre>	utility	21.2
max_sizehist(long);	utility	21.2
max_storages(long);	utility	21.2
<pre>max_tables(long);</pre>	utility	21.2
mdlstat();	utility	19.3
-	•	

20. Reserved Words		
meter(name)	meter	13.1
<pre>meter_cnt(METER);</pre>	meter	13.7
<pre>meter_confidence(METER);</pre>	meter	13.5
<pre>meter_histogram(METER, long, double, double);</pre>	meter	13.4
<pre>meter_ip_table(METER);</pre>	meter	13.7
<pre>meter_name(METER);</pre>	meter	13.7
<pre>meter_rate(METER);</pre>	meter	13.7
<pre>meter_run_length(METER, double, double, double);</pre>	meter	13.5
<pre>meter_start_time(METER);</pre>	meter	13.7
<pre>meter_summary();</pre>	meter	13.7
<pre>msg_cnt(MBOX);</pre>	mailbox	13.7
<pre>msg_content(MSG_PTR);</pre>	mailbox	9.6
negative_binomial(sn,ps)	random	18.1
next_msg(MSG_PTR);	mailbox	9.6
next_process(PROCESS_PTR);	process	9.1
normal(mean,stddev)	random	18.1
normal2(mean,stddev)	random	18.1
note_entry(QTABLE);	qtable	12.2
note_exit(QTABLE);	qtable	12.2
note_passage(METER);	meter	13.2
note_state(QTABLE, long);	qtable	12.2
note_value(QTABLE, long);	qtable	12.2
<pre>num_busy(FACILITY);</pre>	facility	4.14
num_events(EVENT*);	facility	7.13
num_servers(FACILITY);	facility	4.14
pareto(a)	random	18.1
	•	

	201 110001100 11010	<u> </u>
permanent_table(name)	table	11.1
poisson(mean)	random	18.1
<pre>prc_shr(FACILITY, double);</pre>	facility	4.11
<pre>pre_res(FACILITY, double);</pre>	facility	4.11
<pre>pre_rst(FACILITY, double);</pre>	facility	4.11
<pre>preempts(FACILITY);</pre>	facility	4.14
<pre>print_csim_error(long);</pre>	utility	21.5
priority()	process	3.6
<pre>proc_csim_args(int*, char***);</pre>	utility	21.3
process_class(name)	process_class	17.1
process_name();	process	3.6
<pre>qlen(FACILITY);</pre>	facility	4.14
<pre>qlength(FACILITY);</pre>	facility	4.14
qtable(name)	qtable	12.1
<pre>qtable_batch_count(QTABLE);</pre>	qtable	12.7
qtable_batch_size(QTABLE);	qtable	12.7
<pre>qtable_cnt(QTABLE);</pre>	qtable	12.7
<pre>qtable_conf_accuracy(QTABLE, double);</pre>	qtable	12.7
<pre>qtable_conf_halfwidth(QTABLE, double);</pre>	qtable	12.7
<pre>qtable_conf_lower(QTABLE, double);</pre>	qtable	12.7
<pre>qtable_conf_mean(QTABLE);</pre>	qtable	12.7
<pre>qtable_conf_upper(QTABLE, double);</pre>	qtable	12.7
<pre>qtable_confidence(QTABLE);</pre>	qtable	12.5
<pre>qtable_converged(QTABLE);</pre>	qtable	12.5
qtable_cur(QTABLE);	qtable	12.7
<pre>qtable_current(QTABLE);</pre>	qtable	12.7
<pre>qtable_cv(QTABLE);</pre>	qtable	12.7
L		

<pre>qtable_dbl_current(QTABLE);</pre>	qtable	12.7
<pre>qtable_dbl_entries(QTABLE);</pre>	qtable	12.7
<pre>qtable_dbl_exits(QTABLE);</pre>	qtable	12.7
qtable_dbl_initial(QTABLE);	qtable	12.7
<pre>qtable_dbl_max(QTABLE);</pre>	qtable	12.7
<pre>qtable_dbl_min(QTABLE);</pre>	qtable	12.7
<pre>qtable_dbl_range(QTABLE);</pre>	qtable	12.7
<pre>qtable_entries(QTABLE);</pre>	qtable	12.7
qtable_exits(QTABLE);	qtable	12.7
<pre>qtable_histogram(QTABLE, long, long, long);</pre>	qtable	12.4
<pre>qtable_histogram_bucket(QTABLE, long);</pre>	qtable	12.7
qtable_histogram_high(QTABLE);	qtable	12.7
<pre>qtable_histogram_low(QTABLE);</pre>	qtable	12.7
<pre>qtable_histogram_num(QTABLE);</pre>	qtable	12.7
<pre>qtable_histogram_total(QTABLE);</pre>	qtable	12.7
<pre>qtable_histogram_width(QTABLE);</pre>	qtable	12.7
<pre>qtable_initial(QTABLE);</pre>	qtable	12.7
<pre>qtable_max(QTABLE);</pre>	qtable	12.7
qtable_mean(QTABLE);	qtable	12.7
<pre>qtable_min(QTABLE);</pre>	qtable	12.7
<pre>qtable_moving_window(QTABLE, long);</pre>	qtable	12.6
<pre>qtable_name(QTABLE);</pre>	qtable	12.7
qtable_range(QTABLE);	qtable	12.7
<pre>qtable_run_length(QTABLE, double, double, double);</pre>	qtable	12.7
qtable_stddev(QTABLE);	qtable	12.7
<pre>qtable_sum(QTABLE);</pre>	qtable	12.7

	201 110001100 11010	<u> </u>
<pre>qtable_sum_square(QTABLE);</pre>	qtable	12.7
<pre>qtable_summary();</pre>	qtable	12.3
<pre>qtable_var(QTABLE);</pre>	qtable	12.7
qtable_window_size(QTABLE);	qtable	12.6
queue(x)	event	7.4
<pre>queue_any(EVENT*);</pre>	event	7.12
queue_cnt(EVENT);	event	7.13
random(mn,mx)	random	18.1
receive(mb,msg)	mailbox	8.3
receive_any(MBOX*, long*);	mailbox	8.7
record(double, TABLE);	table	11.2
record_value(QTABLE, double);	table	12.2
release(FACILITY);	facility	4.3
release_server(FACILITY, long);	facility	4.6
remove_store(STORE, long);	storage	5.11
report();	utility	19.1
report_box(BOX);	box	14.3
report_boxes();	box	14.3
report_buffers();	buffer	6.4
report_classes();	process_class	17.3
report_events();	event	7.10
report_facilities();	facility	4.4
report_hdr();	utility	19.1
report_mailboxes());	mailbox	8.7
report_meter(METER);	meter	13.3
report_meters();	meter	13.3
report_qtable(QTABLE);	qtable	12.3

Zo. Neserved Words		
report_qtable_dbl(QTABLE);	qtable	12.3
report_qtables();	qtable	12.3
report_storages();	storage	5.4
report_table(TABLE);	table	11.3
report_tables();	table	11.3
rerun()	utility	21.4
reseed(STREAM, long);	random	18.2
reserve(FACILITY);	facility	4.3
reset()	utility	21.4
reset_box(BOX);	box	14.9
reset_boxes();	box	14.9
reset_buffer(BUFFER b);	buffer	6.5
reset_buffers();	buffer	6.5
reset_event(EVENT);	event	7.11
reset_events();	event	7.11
reset_facilities();	facility	4.5
reset_facility(FACILITY);	facility	4.5
<pre>reset_mailbox(MBOX);</pre>	mailbox	8.8
reset_mailboxes();	mailbox	8.8
<pre>reset_meter(METER);</pre>	meter	13.9
reset_meters();	meter	13.9
reset_process_class(CLASS);	process_class	17.5
reset_process_classes();	process_class	17.5
reset_qtable(QTABLE);	qtable	12.9
reset_qtables();	qtable	12.9
reset_storage(STORE);	storage	5.5
reset_storages();	storage	5.5
	1	ı

	201 110001 100 1101	
<pre>reset_table(TABLE);</pre>	table	11.9
reset_tables();	table	11.9
resp(FACILITY);	facility	4.11
restart_process(PROCESS_PTR);	process	9.1
<pre>rnd_pri(FACILITY, double);</pre>	facility	4.11
<pre>rnd_rob(FACILITY, double);</pre>	facility	4.11
send(mb,msg)	mailbox	8.2
serv(FACILITY);	facility	4.14
server_completions(FACILITY, long);	facility	4.14
server_serv(FACILITY, long);	facility	4.14
server_tput(FACILITY, long);	facility	4.14
server_util(FACILITY, long);	facility	4.14
service_disp(FACILITY);	facility	4.14
set(ev)	event	7.6
set_conclude_flag();	utility	21.4.3
set_err_handler(EH);	utility	21.5
set_error_file(FILE*);	utility	21.6
set_initial_value(QTABLE, double);	qtable	12.1
set_input_file(FILE*);	utility	21.6
<pre>set_loaddep(FACILITY, double*, long);</pre>	facility	4.11
<pre>set_model_name(const char*);</pre>	utility	19.1
<pre>set_moving_qtable(QTABLE, long);</pre>	qtable	12.6
<pre>set_moving_table(TABLE, long);</pre>	table	11.6
<pre>set_name_box(BOX, const char*);</pre>	box	14.6
<pre>set_name_event(EVENT, const char*);</pre>	event	7.8
<pre>set_name_facility(FACILITY, const char*);</pre>	facility	4.1
<pre>set_name_mailbox(MBOX, const char*);</pre>	mailbox	8.10

<pre>set_name_meter(METER, const char*);</pre>	meter	13.8
<pre>set_name_process_class(CLASS, const char*);</pre>	process_class	17.4
<pre>set_name_qtable(QTABLE, const char*);</pre>	qtable	12.8
<pre>set_name_storage(STORE, const char*);</pre>	storage	5.1
<pre>set_name_table(TABLE, const char*);</pre>	table	11.8
set_output_file(FILE*);	utility	21.6
set_priority(long);	process	3.5
set_process_class(CLASS);	process_class	17.2
<pre>set_process_priority(PROCESS_PTR, long);</pre>	process	9.1
<pre>set_process_struct(PROCESS_PTR, void*);</pre>	process	9.1
<pre>set_servicefunc(FACILITY, SF);</pre>	facility	4.11
<pre>set_this_struct(void *);</pre>	process	9.1
<pre>set_timeslice(FACILITY, double);</pre>	facility	4.11
set_trace_file(FILE*);	utility	21.6
<pre>setup_empirical(const long, const double*, double*, long*);</pre>	random	18.1
simtime();	utility	2.3
state(ev)	event	7.13
status(fac)	facility	4.14
status_buffers();	buffer	6.1
status_events();	event	7.14
status_facilities();	facility	4.15
status_mailboxes();	mailbox	8.13
status_next_event_list();	utility	19.4
status_processes();	process	3.7
status_storages();	storage	5.13
storage(name,amt)	storage	5.1

	201 110001100 110100	
storage_busy_amt(STORE);	storage	5.12
storage_capacity(STORE);	storage	9.3
storage_first_process(STORE);	storage	9.3
storage_insert_process(STORE, PROCESS_PTR);	storage	9.3
storage_last_process(STORE);	storage	9.3
storage_name(STORE);	storage	5.12
storage_number_amt(STORE);	storage	5.12
storage_qlength(STORE);	storage	5.12
storage_queue_cnt(STORE);	storage	5.12
storage_release_cnt(STORE);	storage	5.12
storage_release_total(STORE);	storage	5.12
storage_remove_process(STORE, PROCESS_PTR);	storage	9.3
storage_request_amt(STORE);	storage	5.12
storage_request_cnt(STORE);	storage	5.12
storage_request_total(STORE);	storage	5.12
storage_set(arr,name,size,n)	storage	5.6
storage_time(STORE);	storage	5.12
storage_waiting_amt(STORE);	storage	5.12
stream()	random	18.3
<pre>stream_bernoulli(STREAM, double);</pre>	random	18.5
<pre>stream_beta(STREAM, double, double, double);</pre>	random	18.5
<pre>stream_binomial(STREAM, double, long);</pre>	random	18.5
stream_cauchy(STREAM, double, double);	random	18.5
stream_empirical(NIL,n,cut,als,val)	random	18.5
<pre>stream_empirical(STREAM, const long, double*, long*, const double*);</pre>	random	18.5
<pre>stream_erlang(STREAM, double, double);</pre>	random	18.5
L		

<pre>stream_erlang2(STREAM, double, double);</pre>	random	18.5
<pre>stream_erlangn(STREAM, double, long);</pre>	random	18.5
stream_expntl(mn)	random	18.5
stream_exponential	random	18.5
stream_exponential(STREAM, double);	random	18.5
stream_gamma(STREAM, double, double);	random	18.5
stream_geometric(STREAM, double);	random	18.5
<pre>stream_hyperx(STREAM, double, double);</pre>	random	18.5
<pre>stream_hypoexponential(STREAM, double, double);</pre>	random	18.5
<pre>stream_lognormal(STREAM, double, double);</pre>	random	18.5
stream_negative_binomial(NIL,sn,ps)	random	18.5
stream_normal(NIL,mean,stddev)	random	18.5
stream_normal2(STREAM, double, double);	random	18.5
stream_pareto(STREAM, double);	random	18.5
stream_poisson(STREAM, double);	random	18.5
stream_prob(STREAM);	random	18.5
stream_prob(void*);	random	18.5
stream_random_int(s,mn,mx)	random	18.5
<pre>stream_triangular(STREAM, double, double, double);</pre>	random	18.5
<pre>stream_uniform(STREAM, double, double);</pre>	random	18.5
stream_uniform_int(STREAM, long, long);	random	18.5
stream_uniform01(STREAM);	random	18.5
stream_weibull(STREAM, double, double);	random	18.5
<pre>stream_zipf(STREAM, long);</pre>	random	18.5
<pre>stream_zipf_sum(STREAM, long, double *);</pre>	random	18.5
<pre>synchronous_facility(FACILITY, double, double);</pre>	facility	4.11

<pre>synchronous_send(MBOX, long);</pre>	mailbox	8.5
<pre>synchronous_storage(STORE, double, double);</pre>	storage	5.8
table(name)	table	11.1
table_batch_count(TABLE);	table	11.7
table_batch_size(TABLE);	table	11.7
table_cnt(TABLE);	table	11.7
table_conf_accuracy(TABLE, double);	table	11.7
table_conf_halfwidth(TABLE, double);	table	11.7
table_conf_lower(TABLE, double);	table	11.7
table_conf_mean(TABLE);	table	11.7
table_conf_upper(TABLE, double);	table	11.7
table_confidence(TABLE);	table	11.7
table_converged(TABLE);	table	11.7
table_cv(TABLE);	table	11.7
table_hist(TABLE);	table	11.7
table_histogram(TABLE, long, double, double);	table	11.7
table_histogram_bucket(TABLE, long);	table	11.7
table_histogram_high(TABLE);	table	11.7
table_histogram_low(TABLE);	table	11.7
table_histogram_num(TABLE);	table	11.7
table_histogram_total(TABLE);	table	11.7
table_histogram_width(TABLE);	table	11.7
table_max(TABLE);	table	11.7
table_mean(TABLE);	table	11.7
table_min(TABLE);	table	11.7
table_moving_window(TABLE, long);	table	11.7
table_name(TABLE);	table	11.7

table_range(TABLE);	table	11.7
<pre>table_run_length(TABLE, double, double, double);</pre>	table	11.5
table_stddev(TABLE);	table	11.7
table_sum(TABLE);	table	11.7
table_sum_square(TABLE);	table	11.7
table_summary();	table	11.7
table_var(TABLE);	table	11.7
table_window_size(TABLE);	table	11.6
tabulate(TABLE, double);	table	11.2
terminate()	process	3.4
this_process();	process	9.1
<pre>time_of_day();</pre>	utility	21.1
<pre>timed_alloc(STORE, long, double);</pre>	storage	5.7
<pre>timed_allocate(long, STORE, double);</pre>	storage	5.7
<pre>timed_queue(EVENT, double);</pre>	event	7.5
<pre>timed_queue_any(EVENT*, double);</pre>	event	7.12
<pre>timed_receive(MBOX, long*, double);</pre>	mailbox	8.4
<pre>timed_receive_any(MBOX*, long*, double);</pre>	mailbox	8.9
<pre>timed_reserve(FACILITY, double);</pre>	facility	4.9
<pre>timed_synchronous_send(MBOX, long, double);</pre>	mailbox	8.6
<pre>timed_wait(EVENT, double);</pre>	event	7.3
<pre>timed_wait_any(EVENT*, double);</pre>	event	7.12
timeslice(FACILITY);	facility	4.11
tput(FACILITY);	facility	4.14
<pre>trace_msg(char *);</pre>	utility	20.5
<pre>trace_object(char *);</pre>	utility	20.3

	Lo. Itooci voa viola	•
<pre>trace_off();</pre>	utility	20.1
<pre>trace_on();</pre>	utility	20.1
<pre>trace_process(const char *);</pre>	utility	20.2
triangular(mn,mx,mode)	random	18.1
uniform(mn,mx)	random	18.1
uniform_int(mn,mx)	random	18.1
uniform01()	random	18.1
use(FACILITY, double);	facility	4.2
util(FACILITY);	facility	4.14
wait(ev)	event	7.2
<pre>wait_any(EVENT*);</pre>	event	7.13
wait_cnt(EVENT);	event	7.13
weibull(shape,scale)	random	18.1
zipf(n)	random	18.1
zipf_sum(n,sum)	random	18.1

# 26.2 Data Structures

BUFFER	used to define a buffer class
CLASS	used to define a process class
EVENT	used to define an event or event_set
FACILITY	used to define a facility or facility_set
MBOX	used to define a mailbox
MSG_PTR	used to define a pointer to a message
PROCESS_PT	used to define a pointer to a process
R	
QTABLE	used to define a qtable
STORE	used to define a storage
STREAM	used to define a stream of random numbers
TABLE	used to define a table
TIME	used to define time variables (double precision)

# 26.3 Constant Values

BUSY FREE	status of facility
NIL	0
OCC NOT_OCC	status of event (occurred)
EVENT_OCCURRED TIMED_OUT	value of timed_operation
MAXCLASSES MAXEVNTS MAXFACS	default maximum number of process classes default maximum number of events default maximum number of facilities
MAXHISTS MAXMBOXS	default maximum number of historgrams default maximum number of mailboxes
MAXMSGS MAXPROCS MAXQTBLS	default maximum number of messages default maximum number of processes
MAXSTORS MAXSERVS	default maximum number of queue histograms default maximum number of storage units default maximum number of server/facility
MAXSIZEH MAXTBLS	default maximum size of a histogram default maximum number of tables

# 26.4 Special Structures

default class	class that all process belong to initially
i deladit class	I class that all process belong to initially

## 26.5 Legacy Functions

#### These are compatible with CSIM 18 and prior versions.

```
add_store
                                      add_store(10, s)
allocate
                                      allocate(100, s)
                                      n = current_state(qt);
current state
deallocate
                                      deallocate(100, s)
                                      n = events_processed();
events_processed
exit csim
                                      exit csim();
expntll
                                      x = expntl(xmn);
free
                                      UNIX routine used in CSIM
                                      h = histogram(name, num, low, high);
histogram
initialize_csim
                                      initialize_csim();
                                      UNIX routine used in CSIM
log
malloc
                                      UNIX routine used in CSIM
permanent_histogram
                                      h = permanent_histogram(name, n, lo, hi);
permanent_qhistogram
                                      qh = permanent_qhistogram(name, n);
prob
                                      x = prob():
qhistogram
                                      qh = qhistogram(name, n);
qhistogram_bucket_cnt
                                      n = qhistogram_bucket_cnt(qh,i);
ghistogram bucket time
                                      x = ghistogram bucket time(gh,i);
qhistogram_num
                                      n = qhistogram_num(qh);
qhistogram_time
                                      x = qhistogram_time(qh);
                                      i = qtable_cnt(qt);
atable cnt
gtable cur
                                      i = qtable_cur(qt);
qtable_qlen
                                      x = qtable_qlen(qt);
gtable gtime
                                      x = \text{qtable qtime(qt)};
qtable_qtsum
                                      x = qtable_qtsum(qt);
rand
                                      UNIX routine used in CSIM
random
                                      i = random(i1, i2);
record
                                      record(x, tbl)
                                      set_log_file(fd);
set_log_file
set_moving_qtable
                                      set_moving_qtable(qt, n);
set_moving_table
                                      set_moving_table(tbl, n);
stream_expntl
                                      x = stream_expntl(s, x1);
stream_init
                                      s = stream_init(i);
stream prob
                                      x = stream prob(s);
                                      i = stream_random(s, i1, i2);
stream_random
stream reset prob
                                      stream_reset_prob(s, i);
trace_sw
```